

# Configure Anycast RP Using MSDP for NX-OS

## Contents

---

### [Introduction](#)

### [Prerequisites](#)

[Requirements](#)

[Components Used](#)

### [Background Information](#)

### [Configure](#)

[Network Diagram](#)

[Configure Unicast and Multicast before MSDP](#)

[Configure MSDP Peering on all RPs in the Network](#)

### [Verify](#)

### [Troubleshoot](#)

[MSDP Peering Stuck in Listening State](#)

[Multicast \(S, G\)s not Shared](#)

### [Related Information](#)

---

## Introduction

This document describes how to configure Anycast RP using MSDP on a Nexus switch running in NX-OS mode.

## Prerequisites

### Requirements

It is recommended that you have knowledge of these topics:

- NX-OS Unicast Routing
- NX-OS Multicast Routing
- [Multicast Source Discovery Protocol \(MSDP\)](#)
- Anycast Rendezvous Point (Anycast RP)

### Components Used

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

The information in this document is based on Cisco Nexus 9000 with NXOS version 9.3.9.


## Background Information

Although the protocol Anycast-RP is more commonly used to share the role of RP between two or more

PIM routers in the same routing domain, [MSDP can also be used](#).

## Configure

### Network Diagram



**Note:** In the previous diagram, the blue links are labeled as **Layer 2 Interface** and the red links are labeled as **Layer 3 Interface**.

### Configure Unicast and Multicast before MSDP

Before MSDP can be configured, unicast and multicast must be configured on all the layer 3 Nexus switches including the RPs. In this example, EIGRP was configured on all Layer 3 interfaces and ICMP pings were successful from source to receiver.

IGMP is configured on layer 3 interfaces by default. However, you must enable PIM on the layer 3 interfaces as well as statically configure the rp-address that you plan to use on RP-1 and RP-2:

FHR-1:

feature pim

ip pim rp-address 10.1.1.1 group-list 224.0.0.0/4

interface Vlan87

ip pim sparse-mode

interface Ethernet1/7

ip pim sparse-mode

interface Ethernet1/9

ip pim sparse-mode

FHR-2:

feature pim

ip pim rp-address 10.1.1.1 group-list 224.0.0.0/4

interface Vlan87

ip pim sparse-mode

interface Ethernet1/7

ip pim sparse-mode

interface Ethernet1/9

ip pim sparse-mode

RP-1:

feature pim

ip pim rp-address 10.1.1.1 group-list 224.0.0.0/4

interface loopback0

ip pim sparse-mode

interface Ethernet1/53

ip pim sparse-mode

interface Ethernet1/54

ip pim sparse-mode

RP-2:

feature pim

ip pim rp-address 10.1.1.1 group-list 224.0.0.0/4

interface loopback0

ip pim sparse-mode

interface Ethernet1/53

ip pim sparse-mode

```
interface Ethernet1/54
  ip pim sparse-mode
```

```
LHR-1:
feature pim
```

```
ip pim rp-address 10.1.1.1 group-list 224.0.0.0/4
```

```
interface Vlan5
  ip pim sparse-mode
```

```
interface Ethernet1/53
  ip pim sparse-mode
```

```
interface Ethernet1/54
  ip pim sparse-mode
```

```
LHR-2:
feature pim
```

```
ip pim rp-address 10.1.1.1 group-list 224.0.0.0/4
```

```
interface Vlan5
  ip pim sparse-mode
```

```
interface Ethernet1/53
  ip pim sparse-mode
```

```
interface Ethernet1/54
  ip pim sparse-mode
```

## **Configure MSDP Peering on all RPs in the Network**

Each Nexus switch that is a member of the Anycast RP set must be configured to peer with all other Nexus switches. In this example, RP-1 and RP-2 are both configured as peers:

```
RP-1:
feature msdp
```

```
ip msdp originator-id loopback1
ip msdp peer 10.1.1.3 connect-source loopback1
ip msdp mesh-group 10.1.1.3 rp-mesh
```

```
interface loopback0
  description Anycast RP Address
  ip address 10.1.1.1/32
  ip router eigrp 1
  ip pim sparse-mode
```

```
interface loopback1
  description MSDP Originator ID
  ip address 10.1.1.2/32
  ip router eigrp 1
```


```
RP-2:
feature msdp

ip msdp originator-id loopback1
ip msdp peer 10.1.1.2 connect-source loopback1
ip msdp mesh-group 10.1.1.2 rp-mesh

interface loopback0
  description Anycast RP Address
  ip address 10.1.1.1/32
  ip router eigrp 1
  ip pim sparse-mode

interface loopback1
  description MSDP Originator ID
  ip address 10.1.1.3/32
  ip router eigrp 1
```

---

 **Note:** In this example, interface loopback1 is used for MSDP peering and not PIM. For that reason, **ip pim sparse-mode** does not need to be configured on interface loopback1. That said, there is no harm in enabling PIM sparse-mode on interface loopback1.

---

## Verify

MSDP peering is configured correctly when you see the **Connection State** is **Established**. You can see the counter for **(S,G)s Received** increase:

```
<#root>
```

```
RP-1#
```

```
show ip msdp summary
```

```
MSDP Peer Status Summary for VRF "default"
Local ASN: 0, originator-id: 10.1.1.2
```

```
Number of configured peers: 1
Number of established peers: 1
Number of shutdown peers: 0
```

Peer Address	Peer ASN	Connection State	Uptime/ Downtime	Last msg Received	(S,G)s Received
10.1.1.3	0				

```
Established
```

```
01:33:54 never
```

```
1
```

---

 **Note:** The counter for **(S,G)s Received** remains at 0 if there is no multicast in the network.

---

# Troubleshoot

## MSDP Peering Stuck in Listening State

The `show ip msdp summary` command indicates that **Connection State** is in the **Listening** state:

```
<#root>
RP-1#
show ip msdp summary

MSDP Peer Status Summary for VRF "default"
Local ASN: 0, originator-id: 10.1.1.2

Number of configured peers: 1
Number of established peers: 0
Number of shutdown peers: 0

Peer          Peer          Connection    Uptime/   Last msg   (S,G)s
Address       ASN           State         Downtime  Received   Received
10.1.1.3     0
Listening

00:03:27  never      0
```

The likely causes for this issue are:

1. MSDP is incorrectly configured.
2. A connectivity failure caused the MSDP peers to be unable to reach each other.

In this example, assuming the configuration is correct, ethanalyzer can be used to troubleshoot potential packet loss between 10.1.1.2 and 10.1.1.3.

---

 **Note:** Watch [How to perform Ethanalyzer captures on Nexus series switches](#) for more details about ethanalyzer.

---

## Multicast (S, G)s not Shared

If the **Connection State** is **Established** but **(S,G)s Received** is not incrementing, it is likely that MSDP is not configured properly. The most likely cause for this behavior is that the (S,G)s are being discarded due to a detected duplicate rp-address:

```
<#root>
RP-1#
show ip msdp event-history events | i looping

2023 Sep 22 12:13:15.106735 msdp [26860]: : Possible looping SA or duplicate RP address exists, RP 10.1
2023 Sep 22 12:10:10.314695 msdp [26860]: : Possible looping SA or duplicate RP address exists, RP 10.1
```

```
2023 Sep 22 12:09:08.352690 msdp [26860]: : Possible looping SA or duplicate RP address exists, RP 10.1
2023 Sep 22 12:08:06.688953 msdp [26860]: : Possible looping SA or duplicate RP address exists, RP 10.1
2023 Sep 22 12:07:04.403736 msdp [26860]: : Possible looping SA or duplicate RP address exists, RP 10.1
```

By default, the Nexus switch is configured to use the rp-address as the originator-id. However, that causes each MSDP peer to use the same originator-id which causes the (S,G)s to be discarded.

In this example, if the originator-id is not configured, the rp-address 10.1.1.1 from loopback0 is used as the originator-id when it must be a unique IP for Anycast RP to work:

```
RP-1:
feature msdp

ip msdp peer 10.1.1.3 connect-source loopback1
ip msdp mesh-group 10.1.1.3 rp-mesh

interface loopback0
description Anycast RP Address
ip address 10.1.1.1/32
ip router eigrp 1
ip pim sparse-mode

interface loopback1
description MSDP Originator ID
ip address 10.1.1.2/32
ip router eigrp 1
```

```
RP-2:
feature msdp

ip msdp peer 10.1.1.2 connect-source loopback1
ip msdp mesh-group 10.1.1.2 rp-mesh

interface loopback0
description Anycast RP Address
ip address 10.1.1.1/32
ip router eigrp 1
ip pim sparse-mode

interface loopback1
description MSDP Originator ID
ip address 10.1.1.3/32
ip router eigrp
```

The originator-id is confirmed in the MSDP summary show command:

```
<#root>
```

```
RP-1#
```

```
show ip msdp summary
```

MSDP Peer Status Summary for VRF "default"

Local ASN: 0,

originator-id: 10.1.1.1

<--- rp-address from loopback0 is used for the originator-id

Number of configured peers: 1

Number of established peers: 0

Number of shutdown peers: 0

Peer Address	Peer ASN	Connection State	Uptime/Downtime	Last msg Received	(S,G)s Received
10.1.1.3	0	Established	01:33:54	never	0

<#root>

RP-2#

show ip msdp summary

MSDP Peer Status Summary for VRF "default"

Local ASN: 0,

originator-id: 10.1.1.1

<--- rp-address from loopback0 is used for the originator-id


Number of configured peers: 1

Number of established peers: 0

Number of shutdown peers: 0

Peer Address	Peer ASN	Connection State	Uptime/Downtime	Last msg Received	(S,G)s Received
10.1.1.2	0	Established	01:33:54	never	0

---

 **Note:** If MSDP is used to peer between BGP Autonomous Systems (AS)s where the rp-address is typically different, the originator-id can be left default. However, if MSDP is used for Anycast RP, the originator-id must be unique on each MSDP peer.

---

To resolve this issue, **ip msdp originator-id loopback1** must be configured on both of the MSDP peers to ensure that a unique originator-id is used.

## Related Information

- [Cisco Nexus 9000 Series NX-OS Multicast Routing Configuration Guide](#)
- [RFC3618 - Multicast Source Discovery Protocol \(MSDP\)](#)
- [RFC3446 - Anycast Rendezvous Point \(RP\) Mechanism](#)
- [Anycast RP](#)
- [Cisco Technical Support & Downloads](#)