# Configure ISE Guest Accounts with REST API

### **Contents**

Introduction

**Prerequisites** 

Requirements

Components Used

**Background Information** 

Configure

Enable ERS on ISE

Set Up Admin and Sponsor Account for ERS

**Create a Guest Account** 

Read, Update, Delete Guest Data

**Verify** 

**Troubleshoot** 

## Introduction

This document describes how to use Representational State Transfer (REST) API feature to perform guest-related tasks on the Identity Services Engine (ISE). The Cisco Guest API is a REST-based set of operations that provide secure HTTPS and authenticated access to manage Cisco guest users. With the API, one can create, read, update, delete, and search for guest users.

# **Prerequisites**

## Requirements

Cisco recommends that you have the knowledge of these topics:

- ISE
- External RESTful Services
- REST clients like Insomnia, RESTED, etc.

# **Components Used**

The information in this document is based on these software and hardware versions:

- Cisco ISE. Release 2.6
- Insomnia REST client v7.1.1

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Note: The procedure is similar or identical for other ISE versions. You can use these steps

# **Background Information**

In order to use the API, External RESTful Services (ERS) enabled and sponsor authentication needs to be set up in ISE. ERS supports basic authentication and is run over port 9060. The authentication credentials are encrypted and are part of the request header. ERS requires the ISE administrator to assign special privileges to a user to perform operations.

The document will cover these configuration steps:


- 1. Enable ERS on ISE
- Set up admin and sponsor account for ERS
- 3. Create a guest account
- 4. Read, update, delete guest data

# Configure

### **Enable ERS on ISE**

In order to use the REST API feature on ISE, ERS must be enabled.

Navigate to Administration > System > Settings > ERS settings > Enable ERS for read/write as shown in the image.




All the information related to ERS is available as a Software Development Kit (SDK) on HTTPS port 9060 of ISE. This can be accessed after you enable ERS and logging in with an admin account with the privileges of "ERS-Admin" or "ERS-Operator".

## **Set Up Admin and Sponsor Account for ERS**

In order to use ERS, ISE requires an admin account which has the privileges of ERS-Admin or ERS-operator assigned to it. Admin accounts need to be created and added to the respective groups. Alternatively, ERS access works for the Super-Admin account as well.

In order to use APIs for guest features, ERS admin requires raw data of the portals such as the portal ID, guest identity groups, etc. However, in order to read/create/update or delete any guest data, a sponsor account with ERS access enabled is required.

- For the purpose of this document, an internal ISE user account is used as the sponsor.
- Navigate to **Administration > Identity Management > Identities** and add a network access user as shown in the image.



- This user account must be added to one of the sponsor groups.
- The example account is mapped to the default sponsor group named ALL\_ACCOUNTS.
- In order to allow ERS access for this sponsored group, go to Work Centres > Guest Access
   Portal & Components > Sponsor Groups and open the assigned sponsor group.
- Enable the option: Access Cisco ISE guest accounts with the use of the programmatic interface (Guest REST API) as shown in the image.

# Sponsor Can ✓ Update guests' contact information (email, Phone Number) ✓ View/print guests' passwords ☐ Send SMS notifications with guests' credentials ✓ Reset guests' account passwords ✓ Extend guest accounts ✓ Delete guests' accounts ✓ Suspend guests' accounts ☐ Require sponsor to provide a reason ✓ Reinstate suspended guests' accounts ✓ Approve and view requests from self-registering guests ⑥ Any pending accounts ○ Only pending accounts assigned to this sponsor ⑥ ✓ Access Cisco ISE guest accounts using the programmatic interface (Guest REST API)

### **Create a Guest Account**

In order to create a guest account through API, it is necessary that the API call is made to ISE as a sponsor and via a sponsored portal that it recognises.


Step 1. In order to fetch the portal IDs of all the sponsor portals pre-configured on ISE, use any REST client with the information provided here:


Method GET

**URL** https://<ISE-IP>:9060/ers/config/sponsorportal

Credentials
Use ERS Admin credentials
Content-Type: application/xml

Accept: application/xml





### **Expected Output:**

```
<?xml version="1.0" encoding="utf-8" standalone="yes"?>
<ns3:searchResult total="1"
xmlns:ns5="ers.ise.cisco.com"
xmlns:ers-v2="ers-v2"
xmlns:xs="http://www.w3.org/2001/XMLSchema"
xmlns:ns3="v2.ers.ise.cisco.com">
<ns3:resources>
<ns5:resource description="Default portal used by sponsors to create and manage accounts for authorized visitors to securely access the network"
id="274a95f0-2e58-11e9-98fb-0050568775a3" name="Sponsor Portal (default)">
link rel="self" href="https://10.127.197.186:9060/ers/config/sponsorportal/274a95f0-2e58-11e9-98fb-0050568775a3" type="application/xml"/>
</ns5:resource>
</ns3:resource>
</ns3:searchResult></ns3:searchResult></nr>
```

The value of interest is the Portal ID of the Sponsor portal that is intended to be used in order to create guest users. The ID is "274a95f0-2e58-11e9-98fb-0050568775a3" in this example.

Step 2. Use this API call in order to create a guest account. The value of portalID here is the one fetched from Step 1.


Method	POST
URL	https:// <ise-ip>:9060/ers/config/guestuser/</ise-ip>
Credentials	Use sponsor account credentials
Headers	Content-Type:
	application/vnd.com.cisco.ise.identity.guestuser.
	2.0+xml
	Accept:
	application/vnd.com.cisco.ise.identity.guestuser.
	2.0+xml
	xml version="1.0" encoding="UTF-8"?
Body	<ns2:guestuser< td=""></ns2:guestuser<>
	xmlns:ns2="identity.ers.ise.cisco.com">
	<customfields></customfields>
	<guestaccessinfo></guestaccessinfo>

<fromDate>04/25/2020 18:55</fromDate>


<location>Delhi</location> <toDate>04/28/2020 19:55</toDate> <validDays>3</validDays> </guestAccessInfo> <guestInfo> <company>Cisco</company> <emailAddress>abcd@cisco.com</emailAddres</pre> S> <firstName>John/firstName> <lastName>Doe</lastName> <notificationLanguage>English</notificationLang uage> <password>9618</password> <phoneNumber>9999998877</phoneNumber> <smsServiceProvider>Global Default</smsServiceProvider> <userName>johndoe</userName> </guestInfo> <questType>Contractor (default) <personBeingVisited>abcd3@cisco.com</perso</pre> nBeingVisited> <portalld>274a95f0-2e58-11e9-98fb-0050568775a3</portalld> <reasonForVisit>Visiting Bob from Accounting</reasonForVisit> </ns2:guestuser>

**Note**: The body content shown here can be used as a template (available in SDK too). Ensure that the fromDate, toDate corresponds to validDays. The location, guest type and other values must be valid in reference to the ISE used, only then the call will succeed.

**Note:** The credentials used when you make this call must be a valid sponsor account mapped to a sponsor group. ERS admin credentials here will not work. Refer to the previous section of this guide for more details.



**Expected Output:** 



Navigate to ISE GUI > Master GuestReport in order to verify if the account was created:



**Note**: There is no option to specify a customized username and password combination per guest account from a sponsor portal. This API method can be used to fulfil that requirement.

## Read, Update, Delete Guest Data

Here are some example API calls to perform various actions on guest data. All the available options and their formats are available in the SDK.

Get a guest user account details by name:

Method GET


URL https://<ISE-

IP>:9060/ers/config/guestuser/name/{name}

**Credentials** Use sponsor account credentials

Headers Content-Type: application/xml

Accept: application/xml



### **Expected Output:**

```
<ns4:guestuser id="3b967932-86f8-11ea-aafe-72889dc971d1" name="johndoe"</pre>
xmlns:ers="ers.ise.cisco.com"
xmlns:xs="http://www.w3.org/2001/XMLSchema"
xmlns:ns4="identity.ers.ise.cisco.com">
<link rel="self" href="https://10.127.197.186:9060/ers/config/guestuser/name/johndoe"</pre>
type="application/xml"/>
<customFields/>
<questAccessInfo>
<fromDate>04/25/2020 18:55</fromDate>
<location>Delhi</location>
<toDate>04/28/2020 19:55</toDate>
<validDays>3</validDays>
</guestAccessInfo>
<guestInfo>
<company>Cisco</company>
<creationTime>04/25/2020 18:55</creationTime>
<emailAddress>abcd@cisco.com</emailAddress>
<enabled>false
<firstName>John</firstName>
<lastName>Doe
<notificationLanguage>English</notificationLanguage>
<password>9618</password>
<phoneNumber>9999998877</phoneNumber>
<smsServiceProvider>Global Default</smsServiceProvider>
<userName>johndoe</userName>
</guestInfo>
<guestType>Contractor (default)</guestType>
<personBeingVisited>abcd3@cisco.com</personBeingVisited>
<reasonForVisit>Visiting Bob from Accounting/reasonForVisit>
<sponsorUserId>1f7627f0-86f8-11ea-aafe-72889dc971d1/sponsorUserId>
<sponsorUserName>Sponsor_ERS</sponsorUserName>
<status>AWAITING_INITIAL_LOGIN</status>
```

</ns4:guestuser>

```
200 OK
            422 ms
                          1244 B
                                                                                                  3 Minutes Ago +
Preview *
   </
      uning are "ers.ise.cisco.com"
      nulns:xs="http://www.w3.org/2001/APS.Schess"
xmlns:xs4="identity.ors.ise.cisco.com">
          mk rel="self" href="https://19.127.197.186:9968/ers/config/guestuser/name/johndoe"
    type-"application/xml"
        ofrontiste:04/25/2020 18:55(/frontiste)
                   De1h1
                04/28/2020 19:55</tobate)
              eny Cisco!/
              tionTimo:84/25/2828 18:55(/creationTimo:
lAddress:abcd@cisco.com//enailAddress>
                 heal sec
                   tionLanguage English (notificationLangua
•9618 (passwort)
                  99999988774/
                             MGlobal Default (/smsServiceProvider)
                 Contractor (default) (ignestlype)
ngvisited-abcd)@cisco.com/personDo
                  Visit Netflix and chill(/
                   Id>1f7627f8-86f8-11ea-aafe-72880dc971d1</sponsortion1d
                         Sponsor_ERS
               AMAITING INITIAL LOGIN
```

Reset a guest user password:

This requires to first fetch the guest ID from the call and then use it in this API. The guestuser ID is "3b967932-86f8-11ea-aafe-72889dc971d1" in this example.

Method PUT

https://<ISE-

URL IP>:9060/ers/config/guestuser/resetpassword/{id

}

**Credentials** Use sponsor account credentials

Content-Type: application/xml

Accept: application/xml

This method does not allow to specify the new password. ISE will return the output with the new auto-generated password.

#### **Expected output:**

**Headers** 

```
200 OK

<?xml version="1.0" encoding="utf-8" standalone="yes"?>
<ns3:operationResult
xmlns:xs="http://www.w3.org/2001/XMLSchema"
xmlns:ns3="ers.ise.cisco.com">
<attributesList>
<attribute name="password" value="2557"/>
</attributesList>
</ns3:operationResult>
```


• Delete a guest account by name:

Method DELETE https://<ISE-


IP>:9060/ers/config/guestuser/name/{name}

Credentials
Use sponsor account credentials
Content-Type: application/xml

Accept: application/xml



### **Expected output:**



# Verify

There is currently no verification procedure available for this configuration.

# **Troubleshoot**

This section provides information you can use in order to troubleshoot your configuration.

Some common errors and its possible causes:

A guest account creation fails with error:

```
401 Unauthorized

<message type="ERROR" code="CRUD operation exception">

<title>Sponsor does not have permission to access REST Apis</title>
</message>
```

Fix: This means the sponsor account used to make the guest account is mapped to a sponsor group where ERS access is not enabled. Edit the sponsor group that corresponds to this and enable Access Cisco ISE guest accounts with the use of the programmatic interface (Guest REST API).

```
400 Bad Request

<message type="ERROR" code="CRUD operation exception">

<title>Creating GuestUser failed due to

com.cisco.cpm.guestaccess.validation.GuestAccessValidationException: Portal not found for portal
session elfc15a7-a170-4d6a-b02c-0ab7b0bc54ff</title>
```

Fix: The portal ID entered in the call does not exist on ISE or is incorrect. From 'Get' call for sponsor portal, fetch the correct portal ID of the portal.

- API response codes and their possible meanings:
  200 (OK): Indicates the REST API successfully carried out the desired action.
- 201 (Created): Indicates a resource was created inside a collection.
- 204 (No Content): This is usually sent as a response to PUT, POST or DELETE requests.
- 400 (Bad Request): Generic error code for issues like malformed request syntax, invalid parameters, etc. Read the message details if available to understand the cause.
- 401(Unauthorised): This indicates that the action was undertaken with wrong credentials, no credentials or the account is not authorized to perform this action.

500(Internal Server Error): Indicates an issue on the server side. Logs on ISE may help understand the cause.

For more details on REST API usage for ISE, refer to Guest REST API.