



## NAT-PT for IPv6

---

NAT—PT is an IPv6-to-IPv4 translation mechanism, as defined in RFC 2765 and RFC 2766, that allows IPv6-only devices to communicate with IPv4-only devices and vice versa.

This module describes Network Address Translation (NAT)—Protocol Translation (PT) and explains how to configure the feature.

- [Prerequisites for NAT-PT for IPv6, on page 1](#)
- [Restrictions for NAT-PT for IPv6, on page 1](#)
- [Information for NAT-PT for IPv6, on page 2](#)
- [How to Configure NAT-PT for IPv6, on page 4](#)
- [Configuration Examples for NAT-PT for IPv6, on page 13](#)
- [Additional References, on page 15](#)
- [Feature Information for NAT-PT for IPv6, on page 16](#)

## Prerequisites for NAT-PT for IPv6

Before implementing the NAT-PT for IPv6 feature, you must configure IPv4 and IPv6 on device interfaces that need to communicate between IPv4-only and IPv6-only networks.

## Restrictions for NAT-PT for IPv6

- Network Address Translation (NAT)-Protocol Translation (PT) is not supported with Cisco Express Forwarding.
- NAT-PT supports only Domain Naming System (DNS), File Transfer Protocol (FTP), and Internet Control Message Protocol (ICMP) application-layer gateways (ALGs).
- NAT-PT does not provide end-to-end security to networks. The device on which NAT-PT is configured can be a single point of failure in the network.
- Bridge-group virtual interfaces (BVIs) in IPv6 are not supported with NAT-PT and wireless interfaces Dot11Radio.


# Information for NAT-PT for IPv6

## NAT-PT Overview

Network Address Translation (NAT)-Port Translation (PT) for Cisco software based on RFC 2766 and RFC 2765 is a migration tool that helps customers transition their IPv4 networks to IPv6 networks. Using a protocol translator between IPv6 and IPv4 allows direct communication between hosts that use different network protocols. You can use static, dynamic, port address translation, IPv4-mapped definitions for NAT-PT operation.

The figure below shows that NAT-PT runs on a device that is configured between an IPv6 network and an IPv4 network that helps connect an IPv6-only node with an IPv4-only node.

**Figure 1: NAT-PT Basic Operation**



NAT-PT allows direct communication between IPv6-only networks and IPv4-only networks. Dual-stack networks (networks that have IPv4 and IPv6) can have some IPv6-only hosts configured to take advantage of the IPv6 autoconfiguration, global addressing, and simpler management features, and these hosts can use NAT-PT to communicate with existing IPv4-only networks in the same organization.

One of the benefits of NAT-PT is that no changes are required to existing hosts if NAT-PT is configured, because all NAT-PT configurations are performed at the NAT-PT device. Stable IPv4 networks can introduce an IPv6 network and use NAT-PT to communicate between these networks without disrupting the network. For a seamless transition, you can use FTP between IPv4 and IPv6 hosts.

When you configure IPv6, packet fragmentation is enabled by default, to allow IPv4 and IPv6 networks to resolve fragmentation problems. Without the ability to resolve fragmentation, connectivity can be intermittent when fragmented packets are dropped or not interpreted correctly.

We do not recommend the use of NAT-PT to communicate between a dual-stack host and an IPv6-only or IPv4-only host. We do not recommend the use of NAT-PT in a scenario in which an IPv6-only network tries to communicate with another IPv6-only network via an IPv4 backbone or vice versa, because NAT-PT requires a double translation. You can use tunneling techniques for communication in these scenarios.

You can configure one the following operations for NAT-PT, but not all four.

## Static NAT-PT Operation


Static NAT-PT uses static translation rules to map an IPv6 address to an IPv4 address. IPv6 network nodes communicate with IPv4 network nodes using an IPv6 mapping of the IPv4 address that is configured on the NAT-PT device.

The figure below shows how the IPv6-only node named A can communicate with the IPv4-only node named C using NAT-PT. The NAT-PT device is configured to map the source IPv6 address for node A of 2001:DB8:bbbb:1::1 to the IPv4 address 192.168.99.2. NAT-PT is also configured to map the source address of IPv4 node C, 192.168.30.1 to 2001:DB8::a. When packets with a source IPv6 address of node A are received

at the NAT-PT device, these packets are translated to have a destination address that matches node C in the IPv4-only network. You can also configure NAT-PT to match a source IPv4 address and translate the packet to an IPv6 destination address to allow an IPv4-only host to communicate with an IPv6-only host.

If you have multiple IPv6-only or IPv4-only hosts, you may need to configure multiple static NAT-PT mappings. Static NAT-PT is useful when applications or servers require access to a stable IPv4 address, such as accessing an external IPv4 Domain Name System (DNS) server.

**Figure 2: Static NAT-PT Operation**




## Dynamic NAT-PT Operation

Dynamic NAT-PT allows multiple NAT-PT mappings by allocating addresses from a pool of addresses. NAT-PT is configured with a pool of IPv6 and/or IPv4 addresses. At the start of a NAT-PT session a temporary address is dynamically allocated from this pool. The number of addresses available in the address pool determines the maximum number of concurrent sessions. The NAT-PT device records each mapping between addresses in a dynamic state table.

The figure below shows how dynamic NAT-PT operates. The IPv6-only node B can communicate with the IPv4-only node D using dynamic NAT-PT. The NAT-PT device is configured with an IPv6 access list, prefix list, or route map to determine which packets are to be translated by NAT-PT. A pool of IPv4 addresses--10.21.8.1 to 10.21.8.10 in the figure -- is also configured. When an IPv6 packet to be translated is identified, NAT-PT uses the configured mapping rules and assigns a temporary IPv4 address from the configured pool of IPv4 addresses.

**Figure 3: Dynamic NAT-PT Operation**




Dynamic NAT-PT translation operation requires at least one static mapping for the IPv4 Domain Name System (DNS) server.

After the IPv6 to IPv4 connection is established, reply packets going from IPv4 to IPv6 uses the previously established dynamic mapping to translate back from IPv4 to IPv6 and vice versa for an IPv4-only host.

## Port Address Translation

Port Address Translation (PAT), also known as overload configuration, allows a single IPv4 address to be used among multiple sessions by multiplexing on the port number to associate several IPv6 users with a single IPv4 address. PAT can be accomplished through a specific interface or through a pool of addresses. The figure below shows multiple IPv6 addresses from the IPv6 network that is linked to a single IPv4 interface into the IPv4 network.

**Figure 4: Port Address Translation**



## IPv4-Mapped Operation

You can send traffic from your IPv6 network to an IPv4 network without configuring the IPv6 destination address mapping. A packet that arrives at an interface is checked to discover if it has a NAT-PT prefix that was configured with the **ipv6 nat prefix v4-mapped** command. If the prefix matches, then an access-list check is performed to discover if the source address matches the access list or prefix list. If the prefix does not match, the packet is dropped. If the prefix matches, the source address translation is performed.

If a rule is configured for the source address translation, the last 32 bits of the destination IPv6 address is used as the IPv4 destination and a flow entry is created.

With an IPv4-mapping configuration on a device, when the Domain Name System (DNS) application-level gateway (ALG) IPv4 address is converted to an IPv6 address, the IPv6 address is processed and ALGs of the DNS packets from IPv4 network is translated into the IPv6 network.

## How to Configure NAT-PT for IPv6

### Configuring Basic IPv6 to IPv4 Connectivity for NAT-PT for IPv6

Perform this task to configure basic IPv6 to IPv4 connectivity for NAT-PT, which consists of configuring the NAT-PT prefix globally, and enable NAT-PT on an interface. For NAT-PT to be operational, NAT-PT must be enabled on both the incoming and outgoing interfaces.

An IPv6 prefix with a prefix length of 96 must be specified for NAT-PT to use. The IPv6 prefix can be a unique local unicast prefix, a subnet of your allocated IPv6 prefix, or even an extra prefix obtained from your

Internet service provider (ISP). The NAT-PT prefix is used to match a destination address of an IPv6 packet. If the match is successful, NAT-PT will use the configured address mapping rules to translate the IPv6 packet to an IPv4 packet. The NAT-PT prefix can be configured globally or with different IPv6 prefixes on individual interfaces. Using a different NAT-PT prefix on several interfaces allows the NAT-PT router to support an IPv6 network with multiple exit points to IPv4 networks.

## SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ipv6 nat prefix** *ipv6-prefix / prefix-length*
4. **interface** *type number*
5. **ipv6 address** *ipv6-address {/prefix-length | link-local}*
6. **ipv6 nat**
7. **exit**
8. **interface** *type number*
9. **ip address** *ip-address mask [secondary]*
10. **ipv6 nat**

## DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b> <b>Example:</b> Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
Step 2	<b>configure terminal</b> <b>Example:</b> Router# configure terminal	Enters global configuration mode.
Step 3	<b>ipv6 nat prefix</b> <i>ipv6-prefix / prefix-length</i> <b>Example:</b> Router# ipv6 nat prefix 2001:DB8::/96	Assigns an IPv6 prefix as a global NAT-PT prefix. <ul style="list-style-type: none"> <li>• Matching destination prefixes in IPv6 packets are translated by NAT-PT.</li> <li>• The only prefix length supported is 96.</li> </ul>
Step 4	<b>interface</b> <i>type number</i> <b>Example:</b> Router(config)# interface ethernet 3/1	Specifies an interface type and number, and places the router in interface configuration mode.
Step 5	<b>ipv6 address</b> <i>ipv6-address {/prefix-length   link-local}</i> <b>Example:</b> Router(config-if)# ipv6 address 2001:DB8:yyyy:1::9/64	Specifies an IPv6 address assigned to the interface and enables IPv6 processing on the interface.

	Command or Action	Purpose
<b>Step 6</b>	<b>ipv6 nat</b> <b>Example:</b>  Router(config-if)# ipv6 nat	Enables NAT-PT on the interface.
<b>Step 7</b>	<b>exit</b> <b>Example:</b>  Router(config-if)# exit	Exits interface configuration mode, and returns the router to global configuration mode.
<b>Step 8</b>	<b>interface type number</b> <b>Example:</b>  Router(config)# interface ethernet 3/3	Specifies an interface type and number, and places the router in interface configuration mode.
<b>Step 9</b>	<b>ip address ip-address mask [secondary]</b> <b>Example:</b>  Router(config-if)# ip address 192.168.30.9 255.255.255.0	Specifies an IP address and mask assigned to the interface and enables IP processing on the interface.
<b>Step 10</b>	<b>ipv6 nat</b> <b>Example:</b>  Router(config-if)# ipv6 nat	Enables NAT-PT on the interface.

## Configuring IPv4-Mapped NAT-PT

Perform this task to enable customers to send traffic from their IPv6 network to an IPv4 network without configuring IPv6 destination address mapping. This task shows the **ipv6 nat prefix v4-mapped** command configured on a specified interface, but the command could alternatively be configured globally:

### SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **interface type number**
4. **ipv6 nat prefix ipv6-prefix v4-mapped {access-list-name | ipv6-prefix}**

### DETAILED STEPS

	Command or Action	Purpose
<b>Step 1</b>	<b>enable</b> <b>Example:</b>  Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>

	Command or Action	Purpose
Step 2	<b>configure terminal</b> <b>Example:</b> <pre>Router# configure terminal</pre>	Enters global configuration mode.
Step 3	<b>interface type number</b> <b>Example:</b> <pre>Router(config)# interface ethernet 3/1</pre>	Specifies an interface type and number, and places the router in interface configuration mode.
Step 4	<b>ipv6 nat prefix ipv6-prefix v4-mapped</b> <b>{access-list-name   ipv6-prefix}</b> <b>Example:</b> <pre>Router(config-if)# ipv6 nat prefix 2001::/96 v4-mapped v4mapacl</pre>	Enables customers to send traffic from their IPv6 network to an IPv4 network without configuring IPv6 destination address mapping.

## Configuring Mappings for IPv6 Hosts Accessing IPv4 Hosts

Perform this task to configure static or dynamic IPv6 to IPv4 address mappings. The dynamic address mappings include assigning a pool of IPv4 addresses and using an access list, prefix list, or route map to define which packets are to be translated.

### SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. Configure one of the following commands:
  - **ipv6 nat v6v4 source** *ipv6-address ipv4-address*
  - **ipv6 nat v6v4 source** **{list access-list-name | route-map map-name}** **pool name**
4. **ipv6 nat v6v4 pool** *name start-ipv4 end-ipv4 prefix-length prefix-length*
5. **ipv6 nat translation** [**max-entries number**] **{timeout | udp-timeout | dns-timeout | tcp-timeout | finrst-timeout | icmp-timeout}** **{seconds | never}**
6. **ipv6 access-list** *access-list-name*
7. **permit** *protocol {source-ipv6-prefix/prefix-length | any | host source-ipv6-address}* [*operator [port-number]*] **{destination-ipv6-prefix/prefix-length | any | host destination-ipv6-address}**
8. **end**
9. **show ipv6 nat translations** [**icmp | tcp | udp**] [**verbose**]
10. **show ipv6 nat statistics**

### DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b>	Enables privileged EXEC mode.

	Command or Action	Purpose
	<b>Example:</b> Device> enable	<ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
<b>Step 2</b>	<b>configure terminal</b> <b>Example:</b> Device# configure terminal	Enters global configuration mode.
<b>Step 3</b>	Configure one of the following commands: <ul style="list-style-type: none"> <li>• <b>ipv6 nat v6v4 source</b> <i>ipv6-address ipv4-address</i></li> <li>• <b>ipv6 nat v6v4 source</b> {<b>list</b> <i>access-list-name</i>   <b>route-map</b> <i>map-name</i>} <b>pool</b> <i>name</i></li> </ul> <b>Example:</b> Device(config)# ipv6 nat v6v4 source 2001:DB8:yyy:1::1 10.21.8.10 Device(config)# ipv6 nat v6v4 source list pt-list1 pool v4pool	Enables a static IPv6 to IPv4 address mapping using NAT-PT. or Enables a dynamic IPv6 to IPv4 address mapping using NAT-PT.
<b>Step 4</b>	<b>ipv6 nat v6v4 pool</b> <i>name start-ipv4 end-ipv4 prefix-length prefix-length</i> <b>Example:</b> Device(config)# ipv6 nat v6v4 pool v4pool 10.21.8.1 10.21.8.10 prefix-length 24	Specifies a pool of IPv4 addresses to be used by NAT-PT for dynamic address mapping.
<b>Step 5</b>	<b>ipv6 nat translation</b> [ <b>max-entries</b> <i>number</i> ] { <b>timeout</b>   <b>udp-timeout</b>   <b>dns-timeout</b>   <b>tcp-timeout</b>   <b>finrst-timeout</b>   <b>icmp-timeout</b> } { <i>seconds</i>   <b>never</b> } <b>Example:</b> Device(config)# ipv6 nat translation udp-timeout 600	(Optional) Specifies the time after which NAT-PT translations time out.
<b>Step 6</b>	<b>ipv6 access-list</b> <i>access-list-name</i> <b>Example:</b> Device(config)# ipv6 access-list pt-list1	(Optional) Defines an IPv6 access list and enters IPv6 access list configuration mode. <ul style="list-style-type: none"> <li>• The <i>access-list name</i> argument specifies the name of the IPv6 access control list (ACL). IPv6 ACL names cannot contain a space or quotation mark, or begin with a numeral.</li> </ul>
<b>Step 7</b>	<b>permit</b> <i>protocol {source-ipv6-prefix/prefix-length   any   host source-ipv6-address} [operator [port-number]] {destination-ipv6-prefix/prefix-length   any   host destination-ipv6-address}</i> <b>Example:</b> Device(config-ipv6-acl)# permit ipv6 2001:DB8:bbb:1::/64 any	(Optional) Specifies permit conditions for an IPv6 ACL.



	Command or Action	Purpose
<b>Step 8</b>	<b>end</b> <b>Example:</b> Device(config-ipv6-acl)# end	Exits IPv6 access list configuration mode, and returns to privileged EXEC mode.
<b>Step 9</b>	<b>show ipv6 nat translations [icmp   tcp   udp] [verbose]</b> <b>Example:</b> Device# show ipv6 nat translations verbose	(Optional) Displays active NAT-PT translations. <ul style="list-style-type: none"> <li>• Use the optional <b>icmp</b>, <b>tcp</b>, and <b>udp</b> keywords to display detailed information about the NAT-PT translation events for the specified protocol.</li> <li>• Use the optional <b>verbose</b> keyword to display more detailed information about the active translations.</li> </ul>
<b>Step 10</b>	<b>show ipv6 nat statistics</b> <b>Example:</b> Device# show ipv6 nat statistics	(Optional) Displays NAT-PT statistics.

## Configuring Mappings for IPv4 Hosts Accessing IPv6 Hosts

Perform this optional task to configure static or dynamic IPv4 to IPv6 address mappings. The dynamic address mappings include assigning a pool of IPv6 addresses and using an access list, prefix list, or route map to define which packets are to be translated.

### SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. Configure one of the following commands:
  - **ipv6 nat v4v6 source** *ipv6-address ipv4-address*
  - **ipv6 nat v4v6 source list** {*access-list-number | name*} **pool** *name*
4. **ipv6 nat v4v6 pool** *name start-ipv6 end-ipv6 prefix-length prefix-length*
5. **access-list** {*access-list-name | number*} {**deny** | **permit**} [*source source-wildcard*] [**log**]
6. **end**

### DETAILED STEPS

	Command or Action	Purpose
<b>Step 1</b>	<b>enable</b> <b>Example:</b> Device> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
<b>Step 2</b>	<b>configure terminal</b> <b>Example:</b> Device# configure terminal	Enters global configuration mode.

	Command or Action	Purpose
<b>Step 3</b>	Configure one of the following commands: <ul style="list-style-type: none"> <li>• <b>ipv6 nat v4v6 source</b> <i>ipv6-address ipv4-address</i></li> <li>• <b>ipv6 nat v4v6 source list</b> {<i>access-list-number</i>   <i>name</i>} <b>pool name</b></li> </ul> <b>Example:</b> <pre>Device(config)# ipv6 nat v4v6 source 10.21.8.11 2001:DB8:yyyy::2  Device(config)# ipv6 nat v4v6 source list 1 pool v6pool</pre>	Enables a static IPv4 to IPv6 address mapping using NAT-PT.  or  Enables a dynamic IPv4 to IPv6 address mapping using NAT-PT.
<b>Step 4</b>	<b>ipv6 nat v4v6 pool</b> <i>name start-ipv6 end-ipv6 prefix-length prefix-length</i>  <b>Example:</b> <pre>Device(config)# ipv6 nat v4v6 pool v6pool 2001:DB8:yyyy::1 2001:DB8:yyyy::2 prefix-length 128</pre>	Specifies a pool of IPv6 addresses to be used by NAT-PT for dynamic address mapping.
<b>Step 5</b>	<b>access-list</b> { <i>access-list-name</i>   <i>number</i> } { <b>deny</b>   <b>permit</b> } [ <i>source source-wildcard</i> ] [ <b>log</b> ]  <b>Example:</b> <pre>Device(config)# access-list 1 permit 192.168.30.0 0.0.0.255</pre>	Specifies an entry in a standard IPv4 access list.
<b>Step 6</b>	<b>end</b>  <b>Example:</b> <pre>Device(config)# end</pre>	Exits global configuration mode and returns to privileged EXEC mode.

## Configuring PAT for IPv6 to IPv4 Address Mappings

Perform this task to configure Port Address Translation (PAT) for IPv6 to IPv4 address mappings. Multiple IPv6 addresses are mapped to a single IPv4 address or to a pool of IPv4 addresses. Use an access list, a prefix list, or a route map to define which packets must be translated.

### SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. Configure one of the following commands:
  - **ipv6 nat v6v4 source** {**list** *access-list-name* | **route-map** *map-name*} **pool name overload**
  - **ipv6 nat v6v4 source** {**list** *access-list-name* | **route-map** *map-name*} **interface interface name overload**
4. **ipv6 nat v6v4 pool** *name start-ipv4 end-ipv4 prefix-length prefix-length*
5. **ipv6 nat translation** [**max-entries** *number*] {**timeout** | **udp-timeout** | **dns-timeout** | **tcp-timeout** | **finrst-timeout** | **icmp-timeout**} {*seconds* | **never**}
6. **ipv6 access-list** *access-list-name*

7. **permit** *protocol* {*source-ipv6-prefix/prefix-length* | **any** | **host** *source-ipv6-address*} [*operator* [*port-number*]] {*destination-ipv6-prefix/prefix-length* | **any** | **host** *destination-ipv6-address*}
8. **end**

## DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b> <b>Example:</b> Device> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
Step 2	<b>configure terminal</b> <b>Example:</b> Device# configure terminal	Enters global configuration mode.
Step 3	Configure one of the following commands: <ul style="list-style-type: none"> <li>• <b>ipv6 nat v6v4 source</b> {<i>list access-list-name</i>   <b>route-map</b> <i>map-name</i>} <b>pool</b> <i>name</i> <b>overload</b></li> <li>• <b>ipv6 nat v6v4 source</b> {<i>list access-list-name</i>   <b>route-map</b> <i>map-name</i>} <b>interface</b> <i>interface name</i> <b>overload</b></li> </ul> <b>Example:</b> Device(config)# ipv6 nat v6v4 source 2001:DB8:yyyy:1::1 10.21.8.10 Device(config)# ipv6 nat v6v4 source list pt-list1 pool v4pool overload	Enables a dynamic IPv6 to IPv4 address overload mapping using a pool address. or Enables a dynamic IPv6 to IPv4 address overload mapping using an interface address.
Step 4	<b>ipv6 nat v6v4 pool</b> <i>name</i> <i>start-ipv4</i> <i>end-ipv4</i> <b>prefix-length</b> <i>prefix-length</i> <b>Example:</b> Device(config)# ipv6 nat v6v4 pool v4pool 10.21.8.1 10.21.8.10 prefix-length 24	Specifies a pool of IPv4 addresses to be used by NAT-PT for dynamic address mapping.
Step 5	<b>ipv6 nat translation</b> [ <b>max-entries</b> <i>number</i> ] { <b>timeout</b>   <b>udp-timeout</b>   <b>dns-timeout</b>   <b>tcp-timeout</b>   <b>finrst-timeout</b>   <b>icmp-timeout</b> } { <i>seconds</i>   <b>never</b> } <b>Example:</b> Device(config)# ipv6 nat translation udp-timeout 600	(Optional) Specifies the time after which NAT-PT translations time out.
Step 6	<b>ipv6 access-list</b> <i>access-list-name</i> <b>Example:</b> Device(config)# ipv6 access-list pt-list1	(Optional) Defines an IPv6 access list and enters IPv6 access list configuration mode. <ul style="list-style-type: none"> <li>• IPv6 ACL names cannot contain a space or quotation mark, or begin with a numeral.</li> </ul>
Step 7	<b>permit</b> <i>protocol</i> { <i>source-ipv6-prefix/prefix-length</i>   <b>any</b>   <b>host</b> <i>source-ipv6-address</i> } [ <i>operator</i> [ <i>port-number</i> ]]	(Optional) Specifies permit conditions for an IPv6 ACL.

	Command or Action	Purpose
	<p><i>{destination-ipv6-prefix/prefix-length   any   host destination-ipv6-address}</i></p> <p><b>Example:</b></p> <pre>Device(config-ipv6-acl)# permit ipv6 2001:DB8:bbbb:1::/64 any</pre>	
<b>Step 8</b>	<p><b>end</b></p> <p><b>Example:</b></p> <pre>Device(config-ipv6-acl)# end</pre>	Exits IPv6 access list configuration mode and returns to privileged EXEC mode.

## Verifying NAT-PT Configuration and Operation

These commands are optional. Use these commands in any order.

### SUMMARY STEPS

1. **enable**
2. **clear ipv6 nat translation \***
3. **debug ipv6 nat [detailed | port]**

### DETAILED STEPS

	Command or Action	Purpose
<b>Step 1</b>	<p><b>enable</b></p> <p><b>Example:</b></p> <pre>Device&gt; enable</pre>	<p>Enables higher privilege levels, such as privileged EXEC mode.</p> <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
<b>Step 2</b>	<p><b>clear ipv6 nat translation *</b></p> <p><b>Example:</b></p> <pre>Device# clear ipv6 nat translation *</pre>	<p>Clears dynamic Network Address Translation (NAT)-Port Translation (PT) entries from the dynamic translation state table.</p> <ul style="list-style-type: none"> <li>• Use the * keyword to clear all dynamic NAT-PT translations.</li> </ul> <p><b>Note</b> Static translation configuration is not affected by this command.</p>
<b>Step 3</b>	<p><b>debug ipv6 nat [detailed   port]</b></p> <p><b>Example:</b></p> <pre>Device# debug ipv6 nat detail</pre>	Displays debugging messages for NAT-PT translation events.

# Configuration Examples for NAT-PT for IPv6

## Example: Static NAT-PT Configuration

The following example configures the NAT-PT prefix globally, enables NAT-PT on two interfaces, and configures two static NAT-PT mappings. Ethernet interface 3/1 is configured as IPv6 only, and Ethernet interface 3/3 is configured as IPv4 only.

```
interface Ethernet3/1
  ipv6 address 2001:DB8:3002::9/64
  ipv6 enable
  ipv6 nat
!
interface Ethernet3/3
  ip address 192.168.30.9 255.255.255.0
  ipv6 nat
!
ipv6 nat v4v6 source 192.168.30.1 2001:DB8:0::2
ipv6 nat v6v4 source 2001:DB8:bbbb:1::1 10.21.8.10
ipv6 nat prefix 2001:DB8:0::/96
```

## Example: Configuring IPv4-Mapped NAT-PT

The following example shows an access list that permits any IPv6 source address with the prefix 2001::/96 to enter the destination with the 2000::/96 prefix. The destination is translated to the last 32 bit of its IPv6 address; for example: source address is 2001::1 and destination address is 2000::192.168.1.1. The destination is translated to 192.168.1.1 in the IPv4 network.

```
interface gigabitethernet 3/1/1
  ipv6 nat prefix 2000::/96 v4-mapped v4map-acl
  ipv6 access-list v4map-acl
  permit ipv6 2001::/96 2000::/96
```

## Example: Dynamic NAT-PT Configuration for IPv6 Hosts Accessing IPv4 Hosts

The following example configures the NAT-PT prefix globally, enables NAT-PT on two interfaces, and configures one static NAT-PT mapping (used, for example, to access a DNS server). A dynamic NAT-PT mapping is also configured to map IPv6 addresses to IPv4 addresses using a pool of IPv4 addresses named v4pool. The packets to be translated by NAT-PT are filtered using an IPv6 access list named pt-list1. The User Datagram Protocol (UDP) translation entries are configured to time out after 10 minutes. Ethernet interface 3/1 is configured as IPv6 only, and Ethernet interface 3/3 is configured as IPv4 only.

```
interface Ethernet3/1
  ipv6 address 2001:DB8:bbbb:1::9/64
  ipv6 enable
  ipv6 nat
!
interface Ethernet3/3
  ip address 192.168.30.9 255.255.255.0
  ipv6 nat
!
ipv6 nat v4v6 source 192.168.30.1 2001:DB8:0::2
ipv6 nat v6v4 source list pt-list1 pool v4pool
```

```

ipv6 nat v6v4 pool v4pool 10.21.8.1 10.21.8.10 prefix-length 24
ipv6 nat translation udp-timeout 600
ipv6 nat prefix 2001:DB8:1::/96
!
ipv6 access-list pt-list1
 permit ipv6 2001:DB8:bbbb:1::/64 any

```

## Example: Dynamic NAT-PT Configuration for IPv4 Hosts Accessing IPv6 Hosts

The following example configures the NAT-PT prefix globally, enables NAT-PT on two interfaces, and configures one static NAT-PT mapping (used, for example, to access a DNS server). A dynamic NAT-PT mapping is also configured to map IPv4 addresses to IPv6 addresses using a pool of IPv6 addresses named v6pool. The packets to be translated by NAT-PT are filtered using an access list named pt-list2. Ethernet interface 3/1 is configured as IPv6 only, and Ethernet interface 3/3 is configured as IPv4 only.

```

interface Ethernet3/1
 ipv6 address 2001:DB8:bbbb:1::9/64
 ipv6 enable
 ipv6 nat
!
interface Ethernet3/3
 ip address 192.168.30.9 255.255.255.0
 ipv6 nat
!
ipv6 nat v4v6 source list 72 pool v6pool
ipv6 nat v4v6 pool v6pool 2001:DB8:0::1 2001:DB8:0::2 prefix-length 128
ipv6 nat v6v4 source 2001:DB8:bbbb:1::1 10.21.8.0
ipv6 nat prefix 2001:DB8:0::/96
!
access-list 72 permit 192.168.30.0 0.0.0.255

```

## Example: Displaying Dynamic NAT-PT Translations

The following example shows how all dynamic NAT-PT translations are cleared from the dynamic translation state table using the **clear ipv6 nat translation \*** command. After configuring the **clear** command, when you configure the **show ipv6 nat translations** command, only static translation configurations are displayed.

```

Device# clear ipv6 nat translation *

Device# show ipv6 nat translations

Prot  IPv4 source          IPv6 source
----  ----                -
      192.168.123.2      2001:DB8::2
      ---
      192.168.122.10   2001:DB8::10
      ---
      192.168.124.8    2001:DB8:3::8
      ---
      192.168.121.4    2001:DB8:5::4
      ---

```

## Example: Displaying Active NAT-PT Translations

The following sample output from the **show ipv6 nat translations** command displays information about active Network Address Translation (NAT)-Port Translation (PT) translations:

```
Device# show ipv6 nat translations

Prot  IPv4 source          IPv6 source
      IPv4 destination  IPv6 destination
----  ---
      192.168.123.2      2001:DB8::2

----  ---
      192.168.122.10    2001:DB8::10

tcp   192.168.124.8,11047  2001:DB8:3::8,11047
      192.168.123.2,23   2001:DB8::2,23

udp   192.168.124.8,52922  2001:DB8:3::8,52922
      192.168.123.2,69   2001::2,69

udp   192.168.124.8,52922  2001:DB8:3::8,52922
      192.168.123.2,52922 2001:DB8::2,52922

----  192.168.124.8      2001:DB8:3::8
      192.168.123.2    2001:DB8::2

----  192.168.124.8      2001:DB8:3::8
      ---             --- ---
```

## Example: Displaying Information About NAT-PT Statistics

```
Router# show ipv6 nat statistics

Total active translations: 4 (4 static, 0 dynamic; 0 extended)
NAT-PT interfaces:
  Ethernet3/1, Ethernet3/3
Hits: 0 Misses: 0
Expired translations: 0
```

## Additional References

### Related Documents

Related Topic	Document Title
IPv6 addressing and connectivity	<i>IPv6 Configuration Guide</i>
Cisco IOS commands	<i>Master Commands List, All Releases</i>
IPv6 commands	<i>IPv6 Command Reference</i>
Cisco IOS IPv6 features	<i>IPv6 Feature Mapping</i>

**Standards and RFCs**

Standard/RFC	Title
RFCs for IPv6	<i>IPv6 RFCs</i>

**Technical Assistance**

Description	Link
The Cisco Support and Documentation website provides online resources to download documentation, software, and tools. Use these resources to install and configure the software and to troubleshoot and resolve technical issues with Cisco products and technologies. Access to most tools on the Cisco Support and Documentation website requires a Cisco.com user ID and password.	<a href="http://www.cisco.com/cisco/web/support/index.html">http://www.cisco.com/cisco/web/support/index.html</a>

## Feature Information for NAT-PT for IPv6

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to [www.cisco.com/go/cfn](http://www.cisco.com/go/cfn). An account on Cisco.com is not required.

**Table 1: Feature Information for NAT-PT for IPv6**

Feature Name	Releases	Feature Information
NAT-PT: Support for DNS ALG	12.2(13)T	IPv6 provides DNS ALG support.
NAT-PT: Support for FTP ALG	12.3(2)T	IPv6 provides FTP ALG support.
NAT-PT: Support for Fragmentation	12.3(2)T	Packet fragmentation is enabled by default when IPv6 is configured, allowing IPv6 and IPv4 networks to resolve fragmentation problems between the networks.
NAT-PT: Support for Overload	12.3(2)T	This feature allows a single IPv4 address to be used among multiple sessions by multiplexing on the port number to associate several IPv6 users with a single IPv4 address.