

# Configuration d'IPSec entre trois routeurs à l'aide d'adresses privées

## Contenu

[Introduction](#)

[Conditions préalables](#)

[Conditions requises](#)

[Components Used](#)

[Conventions](#)

[Configuration](#)

[Diagramme du réseau](#)

[Configurations](#)

[Vérification](#)

[Dépannage](#)

[Dépannage des commandes](#)

[Informations connexes](#)

## Introduction

Ce document décrit une configuration entièrement maillée avec trois routeurs qui utilisent des adresses privées. L'exemple illustre ces fonctionnalités :

- Encapsulating Security Payload (ESP) - Data Encryption Standard (DES) uniquement
- Clés pré-partagées
- Réseaux privés derrière chaque routeur : 192.168.1.0, 192.168.2.0 et 192.168.3.0
- configuration de la stratégie isakmp et de la carte de chiffrement
- Trafic de tunnel défini avec les commandes **access-list** et **route-map**. Outre la traduction d'adresses de port (PAT), les mappages de route peuvent être appliqués à une traduction d'adresses de réseau statique (NAT) un-à-un sur le logiciel Cisco IOS® version 12.2(4)T2 et ultérieure. Pour plus d'informations, reportez-vous à [NAT - Ability to Use Route Maps with Static Translations Feature Overview](#).

**Remarque** : La technologie de chiffrement est soumise à des contrôles d'exportation. Il est de votre responsabilité de connaître la loi relative à l'exportation des technologies de chiffrement. Si vous avez des questions concernant le contrôle des exportations, veuillez envoyer un courriel à [export@cisco.com](mailto:export@cisco.com).

## [Conditions préalables](#)

## [Conditions requises](#)

Aucune spécification déterminée n'est requise pour ce document.

## Components Used

Les informations contenues dans ce document sont basées sur les versions de matériel et de logiciel suivantes :

- Logiciel Cisco IOS Version 12.3.(7)T.
- Routeurs Cisco configurés avec IPSec.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, make sure that you understand the potential impact of any command.

## Conventions

Pour plus d'informations sur les conventions des documents, référez-vous aux [Conventions utilisées pour les conseils techniques de Cisco](#).


## Configuration

Cette section vous fournit des informations pour configurer les fonctionnalités décrites dans ce document.

**Remarque :** Pour en savoir plus sur les commandes utilisées dans le présent document, utilisez [l'outil de recherche de commandes](#) (clients [inscrits](#) seulement).

## Diagramme du réseau

Ce document utilise la configuration réseau suivante :



## Configurations

Ce document utilise les configurations suivantes :

- [Routeur 1](#)
- [Routeur 2](#)
- [Routeur 3](#)

### Routeur 1

```

Current configuration:
!
version 12.3
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
!
hostname router1
!
boot-start-marker
boot-end-marker
!
!
clock timezone EST 0
no aaa new-model
ip subnet-zero
!
!

```

```
ip audit po max-events 100
no ftp-server write-enable
!

!--- Configure Internet Key Exchange (IKE) policy and !-
-- pre-shared keys for each peer. !--- IKE policy
defined for peers. crypto isakmp policy 4
authentication pre-share

!--- Pre-shared keys for different peers. crypto isakmp
key xxxxxx1234 address 100.228.202.154
crypto isakmp key xxxxxx1234 address 200.154.17.130
!
!

!--- IPsec policies: crypto ipsec transform-set encrypt-
des esp-des
!
!
crypto map combined local-address Serial0

!--- Set the peer, transform-set and encryption traffic
for tunnel peers. crypto map combined 20 ipsec-isakmp
    set peer 100.228.202.154
    set transform-set encrypt-des
    match address 106
crypto map combined 30 ipsec-isakmp
    set peer 200.154.17.130
    set transform-set encrypt-des
    match address 105
!
!
interface Serial0
    ip address 100.232.202.210 255.255.255.252
    ip nat outside
    serial restart-delay 0

!--- Apply the crypto map to the interface. crypto map
combined
!
interface FastEthernet0
    ip address 192.168.1.1 255.255.255.0
    ip nat inside
!
ip classless
ip route 0.0.0.0 0.0.0.0 100.232.202.209
no ip http server
no ip http secure-server
!

!--- Define traffic for NAT. ip nat inside source route-
map nonat interface Serial0 overload

!--- Access control list (ACL) that shows traffic to
encrypt over the tunnel. access-list 105 permit ip
192.168.1.0 0.0.0.255 192.168.3.0 0.0.0.255
access-list 106 permit ip 192.168.1.0 0.0.0.255
192.168.2.0 0.0.0.255

!--- ACL to avoid the traffic through NAT over the
tunnel. access-list 150 deny ip 192.168.1.0 0.0.0.255
192.168.2.0 0.0.0.255
access-list 150 deny ip 192.168.1.0 0.0.0.255
192.168.3.0 0.0.0.255
```

```
!--- ACL to perform NAT on the traffic that does not go
over the tunnel. access-list 150 permit ip 192.168.1.0
0.0.0.255 any

!--- Do not perform NAT on the IPSec traffic. route-map
nonat permit 10
  match ip address 150
!
control-plane
!
!
line con 0
line aux 0
line vty 0 4
!
!
end
```

## Routeur 2

```
Current configuration:
!
version 12.3
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
!
hostname router2
!
boot-start-marker
boot-end-marker
!
!
clock timezone EST 0
no aaa new-model
ip subnet-zero
!
!
ip audit po max-events 100
no ftp-server write-enable
!

!--- Configure IKE policy and pre-shared keys for each
peer. !--- IKE policy defined for peers. crypto isakmp
policy 4
  authentication pre-share

!--- Pre-shared keys for different peers. crypto isakmp
key xxxxxx1234 address 100.228.202.154
crypto isakmp key xxxxxx1234 address 100.232.202.210
!
!

!--- IPSec policies. crypto ipsec transform-set encrypt-
des esp-des
!
!
crypto map combined local-address Ethernet1

!--- Set the peer, transform-set and encryption traffic
for tunnel peers. crypto map combined 7 ipsec-isakmp
set peer 100.232.202.210
```

```

    set transform-set encrypt-des
    match address 105

crypto map combined 8 ipsec-isakmp
    set peer 100.228.202.154
    set transform-set encrypt-des
    match address 106
!
!
!
interface Ethernet0
    ip address 192.168.3.1 255.255.255.0
    ip nat inside
!
interface Ethernet1
    ip address 200.154.17.130 255.255.255.224
    ip nat outside

!--- Apply the crypto map to the interface. crypto map
combined
!
ip classless
ip route 0.0.0.0 0.0.0.0 200.154.17.129
no ip http server
no ip http secure-server
!

!--- Define traffic for NAT. ip nat inside source route-
map nonat interface Ethernet1 overload

!--- ACL shows traffic to encrypt over the tunnel.
access-list 105 permit ip 192.168.3.0 0.0.0.255
192.168.1.0 0.0.0.255
access-list 106 permit ip 192.168.3.0 0.0.0.255
192.168.2.0 0.0.0.255

!--- ACL to avoid the traffic through NAT over the
tunnel. access-list 150 deny ip 192.168.3.0 0.0.0.255
192.168.1.0 0.0.0.255
access-list 150 deny ip 192.168.3.0 0.0.0.255
192.168.2.0 0.0.0.255

!--- ACL to perform NAT on the traffic that does not go
over the tunnel. access-list 150 permit ip any any

!--- Do not perform NAT on the IPsec traffic. route-map
nonat permit 10
    match ip address 150
!
!
!
control-plane
!
!
line con 0
line aux 0
line vty 0 4
!
!
end

```

### Configuration du Routeur 3

```
Current configuration:
!
version 12.3
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
!
hostname router3
!
boot-start-marker
boot-end-marker
!
!
clock timezone EST 0
no aaa new-model
ip subnet-zero
!
!
ip audit po max-events 100
no ftp-server write-enable
!

!--- Configure IKE policy and pre-shared keys for each
peer. !--- IKE policy defined for peers. crypto isakmp
policy 4
  authentication pre-share

!--- Pre-shared keys for different peers. crypto isakmp
key xxxxxx1234 address 100.232.202.210
crypto isakmp key xxxxxx1234 address 200.154.17.130
!
!

!--- IPsec policies: crypto ipsec transform-set encrypt-
des esp-des
!
!

!--- Set the peer, transform-set and encryption traffic
for tunnel peers. crypto map combined local-address
Serial0
crypto map combined 7 ipsec-isakmp
  set peer 100.232.202.210
  set transform-set encrypt-des
  match address 106
crypto map combined 8 ipsec-isakmp
  set peer 200.154.17.130
  set transform-set encrypt-des
  match address 105
!
!
interface Serial0
  ip address 100.228.202.154 255.255.255.252
  ip nat outside
  serial restart-delay 0

!--- Apply the crypto map to the interface. crypto map
combined
!
  interface FastEthernet0
  ip address 192.168.2.1 255.255.255.0
  ip nat inside
!
```

```

ip classless
ip route 0.0.0.0 0.0.0.0 100.228.202.153
no ip http server
no ip http secure-server
!

!--- Define traffic for NAT. ip nat inside source route-
map nonat interface Serial0 overload

!--- ACL that shows traffic to encrypt over the tunnel.
access-list 105 permit ip 192.168.2.0 0.0.0.255
192.168.3.0 0.0.0.255
access-list 106 permit ip 192.168.2.0 0.0.0.255
192.168.1.0 0.0.0.255

!--- ACL to avoid the traffic through NAT over the
tunnel. access-list 150 deny ip 192.168.2.0 0.0.0.255
192.168.3.0 0.0.0.255
access-list 150 deny ip 192.168.2.0 0.0.0.255
192.168.1.0 0.0.0.255

!--- ACL to perform NAT on the traffic that does not go
over the tunnel. access-list 150 permit ip 192.168.2.0
0.0.0.255 any

!--- Do not perform NAT on the IPSec traffic. route-map
nonat permit 10
    match ip address 150
!
!
!
control-plane
!
!
line con 0
line aux 0
line vty 0 4
    login
!
!
end

```

## Vérification

Cette section présente des informations que vous pouvez utiliser pour vous assurer que votre configuration fonctionne correctement.

Certaines commandes **show** sont prises en charge par l'[Output Interpreter Tool](#) (clients enregistrés uniquement), qui vous permet de voir une analyse de la sortie de la commande show.

- **show crypto engine connections active** - Affiche les paquets chiffrés et déchiffrés entre homologues IPSec.
- **show crypto isakmp sa** — Affiche toutes les associations de sécurité actuelles IKE (SA) sur un homologue.
- **show crypto ipsec sa** - Affiche les paramètres utilisés par les SA actuelles (IPSec).

## Dépannage



Cette section fournit des informations que vous pouvez utiliser pour dépanner votre configuration.

## Dépannage des commandes

Certaines commandes **show** sont prises en charge par l'[Output Interpreter Tool](#) (clients enregistrés uniquement), qui vous permet de voir une analyse de la sortie de la commande show.

**Note** : Avant d'émettre des commandes **debug**, consultez [Informations importantes sur les commandes de débogage](#).

**Remarque** : Les débogages suivants doivent être exécutés sur les deux routeurs IPSec (homologues). Les SA doivent être effacées sur les deux homologues.

- **debug crypto isakmp** - Affiche les erreurs au cours de la phase 1.
- **debug crypto ipsec** - Affiche les erreurs pendant la phase 2.
- **debug crypto engine** — **Affiche des informations du moteur de chiffrement.**
- **clear crypto connection *connection-id* [*slot* / *rsm* / *vip*]** : met fin à une session chiffrée en cours. Les sessions chiffrées se terminent normalement lorsque la session expire. Utilisez la commande **show crypto cisco connections** pour connaître la valeur connection-id.
- **clear crypto isakmp** : efface les SA de phase 1.
- **clear crypto sa** : efface les SA de phase 2.

## Informations connexes

- [Page d'assistance IPsec](#)
- [Support technique - Cisco Systems](#)