



# NAT Routemaps Outside-to-Inside Support

The NAT Routemaps Outside-to-Inside Support feature enables you to configure a NAT routemap configuration that allows IP sessions to be initiated from outside the network to inside the network.

This module explains how to configure the NAT Routemaps Outside-to-Inside Support feature.

- [Restrictions for NAT Route Maps Outside-to-Inside Support, on page 1](#)
- [Information About NAT Route Maps Outside-to-Inside Support, on page 1](#)
- [How to Enable NAT Route Maps Outside-to-Inside Support, on page 3](#)
- [Configuration Examples for NAT Route Maps Outside-to-Inside Support, on page 4](#)
- [Additional References for NAT Route Maps Outside-to-Inside Support, on page 4](#)
- [Feature Information for NAT Route Maps Outside-to-Inside Support, on page 5](#)

## Restrictions for NAT Route Maps Outside-to-Inside Support

- Only IP hosts that are part of a route map configuration will allow outside sessions.
- Outside-to-inside support is not available with Port Address Translation (PAT).
- Outside sessions must use an access list.
- Access lists with reversible route maps must be configured to match the inside-to-outside traffic.
- The **match interface** and **match next-hop** commands are not supported for reversible route maps.

## Information About NAT Route Maps Outside-to-Inside Support

### Route Maps Outside-to-Inside Support Design

An initial session from the inside to the outside host is required to trigger a NAT. New translation sessions can then be initiated from outside to the inside host that triggered the initial translation.

When route maps are used to allocate global addresses, the global address can allow return traffic, and the return traffic is allowed only if the return traffic matches the defined route map in the reverse direction. The outside-to-inside functionality remains unchanged (by not creating additional entries to allow the return traffic for a route-map-based dynamic entry) unless you configure the **reversible** keyword with the **ip nat inside source** command.

**Note**

- Access lists with reversible route maps must be configured to match the inside-to-outside traffic.
- Only IP hosts that are part of the route-map configuration will allow outside sessions.
- Outside-to-inside support is not available with PAT.
- Outside sessions must use an access list.
- The **match interface** and **match ip next-hop** commands are not supported for reversible route maps.
- Reversible route maps are not supported for static NAT.

**SUMMARY STEPS**

1. **enable**
2. **configure terminal**
3. **ip nat pool** *name start-ip end-ip netmask netmask*
4. **ip nat inside source route-map** *name pool name* **reversible**
5. **exit**

**DETAILED STEPS**

	<b>Command or Action</b>	<b>Purpose</b>
<b>Step 1</b>	<b>enable</b> <b>Example:</b> <pre>Router&gt; enable</pre>	Enables privileged EXEC mode. <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
<b>Step 2</b>	<b>configure terminal</b> <b>Example:</b> <pre>Router(config)# configure terminal</pre>	Enters global configuration mode.
<b>Step 3</b>	<b>ip nat pool</b> <i>name start-ip end-ip netmask netmask</i> <b>Example:</b> <pre>Router(config)# ip nat pool POOL-A 192.168.201.4 192.168.201.6 netmask 255.255.255.128</pre>	Defines a pool of network addresses for NAT.
<b>Step 4</b>	<b>ip nat inside source route-map</b> <i>name pool name</i> <b>reversible</b> <b>Example:</b> <pre>Router(config)# ip nat inside source route-map MAP-A pool POOL-A reversible</pre>	Enables outside-to-inside initiated sessions to use route maps for destination-based NAT.
<b>Step 5</b>	<b>exit</b> <b>Example:</b> <pre>Router(config)# exit</pre>	Exits global configuration mode and enters privileged EXEC mode.

# How to Enable NAT Route Maps Outside-to-Inside Support

## Enabling NAT Route Maps Outside-to-Inside Support

The NAT Route Maps Outside-to-Inside Support feature enables you to configure a Network Address Translation (NAT) route map configuration. It allows IP sessions to be initiated from the outside to the inside. Perform this task to enable the NAT Route Maps Outside-to-Inside Support feature.

### SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ip nat pool** *name start-ip end-ip netmask netmask*
4. **ip nat pool** *name start-ip end-ip netmask netmask*
5. **ip nat inside source route-map** *name pool name* [reversible]
6. **ip nat inside source route-map** *name pool name* [reversible]
7. **end**

### DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b> <b>Example:</b> Device> enable	Enables privileged EXEC mode.  • Enter your password if prompted.
Step 2	<b>configure terminal</b> <b>Example:</b> Device(config)# configure terminal	Enters global configuration mode.
Step 3	<b>ip nat pool</b> <i>name start-ip end-ip netmask netmask</i> <b>Example:</b> Device(config)# ip nat pool POOL-A 192.168.201.4 192.168.201.6 netmask 255.255.255.128	Defines a pool of network addresses for NAT.
Step 4	<b>ip nat pool</b> <i>name start-ip end-ip netmask netmask</i> <b>Example:</b> Device(config)# ip nat pool POOL-B 192.168.201.7 192.168.201.9 netmask 255.255.255.128	Defines a pool of network addresses for NAT.
Step 5	<b>ip nat inside source route-map</b> <i>name pool name</i> [reversible] <b>Example:</b> Device(config)# ip nat inside source route-map MAP-A pool POOL-A reversible	Enables outside-to-inside initiated sessions to use route maps for destination-based NAT.

	Command or Action	Purpose
Step 6	<b>ip nat inside source route-map <i>name</i> pool <i>name</i> [reversible]</b>  <b>Example:</b> Device(config)# ip nat inside source route-map MAP-B pool POOL-B reversible	Enables outside-to-inside initiated sessions to use route maps for destination-based NAT.
Step 7	<b>end</b>  <b>Example:</b> Device(config)# end	(Optional) Exits global configuration mode and returns to privileged EXEC mode.

## Configuration Examples for NAT Route Maps Outside-to-Inside Support

### Example: Enabling NAT Route Maps Outside-to-Inside Support

The following example shows how to configure a route map A and route map B to allow outside-to-inside translation for a destination-based Network Address Translation (NAT):

```
ip nat pool POOL-A 192.168.201.4 192.168.201.6 netmask 255.255.255.128
ip nat pool POOL-B 192.168.201.7 192.168.201.9 netmask 255.255.255.128
ip nat inside source route-map MAP-A pool POOL-A reversible
ip nat inside source route-map MAP-B pool POOL-B reversible
```

## Additional References for NAT Route Maps Outside-to-Inside Support

### Related Documents

Related Topic	Document Title
Cisco IOS commands	<a href="#">Cisco IOS Master Command List, All Releases</a>
NAT commands	<a href="#">Cisco IOS &lt;&lt;Technology&gt;&gt; Command Reference</a>

**Technical Assistance**

Description	Link
The Cisco Support and Documentation website provides online resources to download documentation, software, and tools. Use these resources to install and configure the software and to troubleshoot and resolve technical issues with Cisco products and technologies. Access to most tools on the Cisco Support and Documentation website requires a Cisco.com user ID and password.	<a href="http://www.cisco.com/cisco/web/support/index.html">http://www.cisco.com/cisco/web/support/index.html</a>

## Feature Information for NAT Route Maps Outside-to-Inside Support

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to [www.cisco.com/go/cfn](http://www.cisco.com/go/cfn). An account on Cisco.com is not required.

**Table 1: Feature Information for NAT Route Maps Outside-to-Inside Support**

Feature Name	Releases	Feature Information
NAT Route Maps Outside-to-Inside Support	12.3(14)T	<p>The NAT Route Maps Outside-to-Inside Support feature enables you to configure a NAT route map configuration that allows IP sessions to be initiated from the outside to the inside.</p> <p>The following command was introduced or modified: <b>ip nat inside.</b></p>

