



Cisco UCS Director Open Automation Getting Started Guide, Release 6.6

First Published: 2018-04-27

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/go/trademarks>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2018 Cisco Systems, Inc. All rights reserved.



CONTENTS

Preface

Preface v

Audience v

Conventions v

Related Documentation vii

Documentation Feedback vii

Obtaining Documentation and Submitting a Service Request vii

CHAPTER 1

New and Changed Information for this Release 1

New and Changed Information 2

CHAPTER 2

Getting Started with Cisco UCS Director Open Automation 3

Cisco UCS Director Open Automation 3

Recommended Tools 4

Setting up Eclipse 4

Downloading the Open Automation SDK Bundle 4

Importing the Cisco UCS Director Open Automation SDK Project into the Eclipse IDE 5

Using EGit to Import the Open Automation SDK Bundle 5

Installing the EGit Plug-In in Eclipse 5

Importing the Open Automation SDK Bundles into Eclipse 6

Upgrading Your Connector to the Current Release 7

Modules 7

Guidelines for Developing a Module 7

Creating a Module 8

Understanding the module.properties File 10

Packaging the Module 12

Deploying a Module on Cisco UCS Director 13

Deleting, Deactivating, and Modifying Connectors 15



Preface

- [Audience, page v](#)
- [Conventions, page v](#)
- [Related Documentation, page vii](#)
- [Documentation Feedback, page vii](#)
- [Obtaining Documentation and Submitting a Service Request, page vii](#)

Audience

This guide is intended primarily for data center administrators who use Cisco UCS Director and who have responsibilities and expertise in one or more of the following:

- Server administration
- Storage administration
- Network administration
- Network security
- Virtualization and virtual machines

Conventions

Text Type	Indication
GUI elements	GUI elements such as tab titles, area names, and field labels appear in this font . Main titles such as window, dialog box, and wizard titles appear in this font .
Document titles	Document titles appear in <i>this font</i> .
TUI elements	In a Text-based User Interface, text the system displays appears in <i>this font</i> .

Text Type	Indication
System output	Terminal sessions and information that the system displays appear in <i>this font</i> .
CLI commands	CLI command keywords appear in this font . Variables in a CLI command appear in <i>this font</i> .
[]	Elements in square brackets are optional.
{x y z}	Required alternative keywords are grouped in braces and separated by vertical bars.
[x y z]	Optional alternative keywords are grouped in brackets and separated by vertical bars.
string	A nonquoted set of characters. Do not use quotation marks around the string or the string will include the quotation marks.
<>	Nonprinting characters such as passwords are in angle brackets.
[]	Default responses to system prompts are in square brackets.
!, #	An exclamation point (!) or a pound sign (#) at the beginning of a line of code indicates a comment line.

**Note**

Means *reader take note*. Notes contain helpful suggestions or references to material not covered in the document.

**Caution**

Means *reader be careful*. In this situation, you might perform an action that could result in equipment damage or loss of data.

**Tip**

Means *the following information will help you solve a problem*. The tips information might not be troubleshooting or even an action, but could be useful information, similar to a Timesaver.

**Timesaver**

Means *the described action saves time*. You can save time by performing the action described in the paragraph.

**Warning****IMPORTANT SAFETY INSTRUCTIONS**

This warning symbol means danger. You are in a situation that could cause bodily injury. Before you work on any equipment, be aware of the hazards involved with electrical circuitry and be familiar with standard practices for preventing accidents. Use the statement number provided at the end of each warning to locate its translation in the translated safety warnings that accompanied this device.

SAVE THESE INSTRUCTIONS

Related Documentation

Cisco UCS Director Documentation Roadmap

For a complete list of Cisco UCS Director documentation, see the *Cisco UCS Director Documentation Roadmap* available at the following URL: http://www.cisco.com/en/US/docs/unified_computing/ucs/ucs-director/doc-roadmap/b_UCSDirectorDocRoadmap.html.

Cisco UCS Documentation Roadmaps

For a complete list of all B-Series documentation, see the *Cisco UCS B-Series Servers Documentation Roadmap* available at the following URL: <http://www.cisco.com/go/unifiedcomputing/b-series-doc>.

For a complete list of all C-Series documentation, see the *Cisco UCS C-Series Servers Documentation Roadmap* available at the following URL: <http://www.cisco.com/go/unifiedcomputing/c-series-doc>.

**Note**

The *Cisco UCS B-Series Servers Documentation Roadmap* includes links to documentation for Cisco UCS Manager and Cisco UCS Central. The *Cisco UCS C-Series Servers Documentation Roadmap* includes links to documentation for Cisco Integrated Management Controller.

Documentation Feedback

To provide technical feedback on this document, or to report an error or omission, please send your comments to ucs-director-docfeedback@cisco.com. We appreciate your feedback.

Obtaining Documentation and Submitting a Service Request

For information on obtaining documentation, using the Cisco Bug Search Tool (BST), submitting a service request, and gathering additional information, see [What's New in Cisco Product Documentation](#).

To receive new and revised Cisco technical content directly to your desktop, you can subscribe to the [What's New in Cisco Product Documentation RSS feed](#). RSS feeds are a free service.



New and Changed Information for this Release

This chapter contains the following sections:

- [New and Changed Information, page 2](#)

New and Changed Information

The following table provides an overview of the significant changes to this guide for the current release. The table does not provide an exhaustive list of all changes, or of all new features in this release.

Table 1: New Features and Changed Behavior in Cisco UCS Director Open Automation, Release 6.6

Feature	Description	Where Documented
Restart not required	Restarting Cisco UCS Director is no longer required to delete, disable, modify, or enable an Open Automation module.	Deleting, Deactivating, and Modifying Connectors , on page 15
Include Open Automation connectors in Resource Groups	Open Automation connectors can now be included as part of resource group in Cisco UCS Director.	Cisco UCS Director Administrator Guide



Getting Started with Cisco UCS Director Open Automation

- [Cisco UCS Director Open Automation, page 3](#)
- [Upgrading Your Connector to the Current Release, page 7](#)
- [Modules, page 7](#)

Cisco UCS Director Open Automation

You can use the Cisco UCS Director Open Automation tools to develop and integrate your own Cisco UCS Director features as modules. You can customize modules to meet your unique needs.

Using the module, you can perform the following functions:

- Develop your own Cisco UCS Director reports and report actions
- Inventory your devices
- Track changes made to the system through your module
- Develop tasks that can be used for workflows
- Develop and schedule repeatable tasks
- Set up new resource limits

The Open Automation SDK bundle includes code samples that provide models, examples, and comments. You can download the SDK bundle with the sample code from [Cisco DevNet](#).

Recommended Tools

We recommend that you use the following tools:

- Java version 1.8
- Eclipse (can be downloaded from www.eclipse.org)

Setting up Eclipse

Before You Begin

Install Java Runtime Environment (JRE) 1.8.

Step 1 In Eclipse, right-click the Cisco UCS Director Open Automation SDK and choose **Properties**.

Step 2 Set the **Java Compiler** to compile against 1.8.

Step 3 Click **OK**.

Note Make sure that you include the Cisco UCS Director Open Automation SDK jar files in your class path. Also make sure that your project setup mirrors the setup provided in the Open Automation SDK sample.

Downloading the Open Automation SDK Bundle

The Cisco UCS Director SDK binaries can be downloaded from the [software download](#) area of Cisco.com or the Cisco [DevNet](#) site. Also, an admin user can download the SDK binaries from Cisco UCS Director.

Step 1 Log in to Cisco UCS Director.

Step 2 On the menu bar, choose **Administration > Downloads**.

Step 3 Choose **Administration > Downloads**.

Step 4 Several files are displayed:

- REST API SDK—`cucsd-rest-api-sdk-bundle.zip`
- PowerShell Console—`console.exe`
- Open Automation SDK—`cucsd-open-auto-sdk-bundle.zip`
- Custom Tasks Script Samples—`cucsd-cloupia-script-bundle.zip`

Choose the **cucsd-open-auto-sdk-bundle.zip** file.

Step 5 Click **Download**.

The file is downloaded to the default download location.

Importing the Cisco UCS Director Open Automation SDK Project into the Eclipse IDE

The following instructions describe how to import the Open Automation SDK bundle into Eclipse. Follow the instructions provided for your development environment if you do not use Eclipse.

-
- Step 1** Download the Open Automation SDK bundle from the [Cisco.com download site](#) or from [Cisco DevNet](#).
 - Step 2** Extract the SDK bundle.
 - Step 3** Save the sample SDK project zip file on your file system.
 - Step 4** Launch Eclipse.
 - Step 5** Choose **File > Import**.
 - Step 6** In the **Import** dialog box, choose **General > Existing Projects into Workspace**.
 - Step 7** Click **Next**.
 - Step 8** Choose **Select root directory** and browse to the location where you extracted the project.
 - Step 9** Click **Finish**.
The project is automatically compiled.
-

Using EGit to Import the Open Automation SDK Bundle

Git with Eclipse (EGit) is an Eclipse plug-in that enables using the distributed version control system Git. EGIt uses a connector plug-in in Eclipse to import the Open Automation SDK bundle into the IDE.

The Eclipse IDE downloaded from the www.eclipse.org site contains support for Git in its default configuration. If the Git functionality is missing in your Eclipse IDE installation, you can use the Eclipse installation manager to install it. See the following:

- [Installing the EGIt Plug-In in Eclipse](#)
- [Importing the Open Automation SDK Bundles into Eclipse](#)

Installing the EGIt Plug-In in Eclipse

-
- Step 1** Log in to Eclipse.
 - Step 2** Choose **Help > Install New Software**.
The **Install** window appears.
 - Step 3** Click the **Add** button available near the **Work with** field.

- The **Add Site** window appears.
- Step 4** Enter the repository location name.
- Step 5** In the **Location** field, copy and paste the following URL: `http://download.eclipse.org/egit/updates/`.
- Step 6** Click **OK** to add the repository location.
The Eclipse Git Team Provider and JGit packages appear.
- Step 7** Check the **Eclipse Git Team Provider (Incubation)** check box.
- Step 8** (Optional) Check the **JGit (Incubation)** check box.
- Step 9** Click **Next**.
The chosen packages appear for verification.
- Step 10** Click **Next**.
- Step 11** Click **I accept the terms of the license agreement**.
- Step 12** Click **Finish**.
All the necessary dependencies and executable are downloaded and installed.
- Step 13** Accept the prompt to restart Eclipse.
-

What to Do Next

Import the open automation SDK bundle from the Git repository into Eclipse and run the SDK bundle.

Importing the Open Automation SDK Bundles into Eclipse

You can use Git to import the Cisco UCS DirectorSDK Bundles into Eclipse.

Before You Begin

You must have a Git account. If you do not have a Git account, sign up for a new account at [GitLab.com](https://gitlab.com).

- Step 1** Log in to Eclipse.
- Step 2** In the **Java** perspective, right-click in the **Package Explorer** pane.
- Step 3** Click **Import**.
- Step 4** Expand **Git**.
- Step 5** Click **Projects from Git**.
- Step 6** Click **Next**.
- Step 7** Click **Clone URI**.
- Step 8** In the **Import Projects from Git** window, perform the following operations:
- a) In the **URI** field, enter the location of the source repository.
Enter one of the following source repository locations:
 - The repository location for the sample code is `https://gitlab.com/CUCSDSDK/OpenAutomationSample.git`.
 - The repository location for the storage module is `https://gitlab.com/CUCSDSDK/OpenAutomationStorage.git`.
 - The repository location for the network module is `https://gitlab.com/CUCSDSDK/OpenAutomationNetwork.git`.
 - The repository location for the compute module is `https://gitlab.com/CUCSDSDK/OpenAutomationCompute.git`.

- The host and repository path are auto-populated.
- b) In the **Authentication** section, enter your Git account credentials.
 - c) Click **Next**.
The branches available in the repository appear.
 - d) Check the branches that you want to clone from the Git repository.
 - e) Click **Next**.
 - f) In the **Directory** field, enter the local destination where you want to save the Open Automation SDK.
 - g) From the **Initial branch** drop-down list, choose **OpenAutomationSDK**.
By default, the remote name is set as **origin**.
 - h) Click **Finish**.
- The Open Automation SDK bundle is imported into Eclipse. You can view the SDK bundle in the Project Explorer.

Upgrading Your Connector to the Current Release

Cisco UCS Director uses a connector to collect the inventory of the other vendor devices for managing those devices.

For more information on upgrading, refer the [Cisco UCS Director Upgrade Guide](#).

Modules

A module is the top-most logical entry point into Cisco UCS Director.

A module can include the following components:

Component	Description
Task	A Workflow Task that can be used as part of a Workflow.
Report	A report that appears in the Cisco UCS Director UI. Reports may (but are not required to) contain clickable actions.
Trigger	A condition that, once satisfied, can be associated with some action. Examples: shutdown VM, start VM, and so on.

Guidelines for Developing a Module

When you develop a module to support new devices, follow these guidelines:

- Develop for a device family so that you have only one module to support all devices in the family.
- Develop a single module to support only devices within the same category. A module should handle only compute devices, network devices, or storage devices. For example, do not develop a module that


supports both a network switch and a storage controller. Instead, develop one module for the network switch and one module for the storage controller.

- Ensure that the devices supported by the same module are similar.
- The same device may come in different models that are meant for distinct purposes. In such cases, it may be appropriate to use different modules to support them.

Creating a Module

The following items must be in place for your custom module to work:

- A class extending `AbstractCloupiaModule`.
- Override the `onStart` method in the Module Class that extends the `AbstractCloupiaModule`.
- A `.feature` file specifying your dependent jars and module class.
- A `module.properties` file is required in the custom module.



Before You Begin

Refer to **FooModule** in the sample project of the Open Automation SDK bundle.

-
- Step 1** Extend the `AbstractCloupiaModule` class and register all your custom components in this class.
- Step 2** Create a `.feature` file that specifies the dependent jars and module class. This file must end with an extension of `.feature`; see `foo.feature` for reference. The best practice is to name this file with your module ID. For more details about the `.feature` file, see [Packaging the Module](#), on page 12.
- Step 3** Add the necessary custom jar files to the `lib` folder.
- Step 4** Package the properties file at the root level of your module jar. Cisco UCS Director provides you with a `properties` file for validation purposes. The SDK sample provides you with a build file that handles the packaging process.
- Note** The content of the `module.properties` file is described in [Understanding the module.properties File](#), on page 10.

- Step 5** In the `module.properties` file, replace the `moduleID` with the ID of the custom module.
- Step 6** From the Eclipse IDE package explorer, right-click the `build.xml` file and run the ANT target build. This action generates the `module.zip` file and save the file to the base directory of your project.

Understanding the `module.properties` File

The `module.properties` file exposes the module to the platform runtime. This file defines properties of the module.

Here is a sample `module.properties` file:

```
moduleID=foo
version=1.0
ucsdVersion=6.5.0.0
category=/foo
format=1.0
name=Foo Module
description=UCSD Open Automation Sample Module
contact=support@cisco.com
key=5591befd056dd39c8f5d578d39c24172
```

The contents are described in the following table:

Table 2: New Module.Properties (module.properties)

Name	Description
moduleID	The unique identifier for the module. This property is mandatory. Example: <code>moduleID=foo</code> Tip We recommend that you restrict this ID to a string of 3 to 5 lowercase alphabetic ASCII characters.
version	The current version of your module. This property is mandatory. Example: <code>version=1.0</code>
ucsdVersion	The version of Cisco UCS Director designed to support your module (with which your module works best). This property is mandatory. Example: <code>ucsdVersion=6.5.0.0</code>

Name	Description
category	<p>The path (/location) where all your tasks must be placed. This property is mandatory.</p> <p>Example:</p> <pre>category=/foo</pre> <p>Note The category parameter is the full path to the location where your tasks are placed. If the tasks module is not validated, the path is set to Open Automation Community Tasks/Experimental. If the tasks module is validated, the tasks are placed relative to the root folder. For example, you can use /Physical Storage Tasks/foo, /Open Automation Community Tasks/Validated/foo, or /foo. In the last case, there is a folder at root level called foo. This feature enables developers to place tasks in categories that are not under Open Automation or in its categories.</p>
format	<p>The version of the format of this module. This property is mandatory. By default, 1.0 version is set for the custom module.</p> <p>Example:</p> <pre>format=1.0</pre> <p>Restriction 1.0 is the only acceptable value here.</p>
name	<p>A user-friendly string that identifies your module in the Open Automation reports.</p> <p>Example:</p> <pre>name=Foo Module</pre>
description	<p>A user-friendly description of what your module does.</p> <p>Example:</p> <pre>description=UCSD Open Automation Sample Module</pre>
contact	<p>An email address that consumers of your module can use to request support.</p> <p>Example:</p> <pre>contact=support@cisco.com</pre>
key	<p>An encrypted key that the Cisco UCS Director Open Automation group provides for validating the module.</p> <p>Example:</p> <pre>key=5591befd056dd39c8f5d578d39c24172</pre>

**Note**

Modifying any mandatory properties invalidates your module. If you change any of the mandatory properties, you must request validation again. The name, description, and contact values, which are not mandatory, can be modified or omitted without revalidation.

Packaging the Module

A module is packaged with all the necessary classes, dependent JAR files, a `module.properties` file, and a `.feature` (pronounced "dot-feature") file. The `.feature` file is placed in the same folder as the root of the project. The `.feature` file shows the JAR associated with this module and the path to the dependent JAR files. The name of the `.feature` file is `<moduleID>-module.feature`.

The following example shows the content of a `.feature` file:

```
{
  jars: [ "features/feature-chargeback.jar",
          "features/chargeback/activation-1.1.jar",
          "features/chargeback/axis2-jaxbri-1.5.6.jar",
          "features/chargeback/bcel-5.1.jar",
          "features/chargeback/jalopy-1.5rc3.jar",
          "features/chargeback/neethi-2.0.5.jar",
          "features/chargeback/antlr-2.7.7.jar",
          "features/chargeback/axis2-jaxws-1.5.6.jar", ]
  features: [ "com.cloupia.feature.oabc.OABCModule" ]
}
```

Before You Begin

We recommend that you use the Apache ANT build tool that comes with Eclipse. You can use any build tool or create the build by hand, but you must deliver a package with the same characteristics as one built with ANT.

SUMMARY STEPS

1. If your module depends on JARs that are not provided with the sample source code, include the jars in the `build.xml` file so that they are packaged in the zip file.
2. From the `build.xml` file, run the ANT target build.

DETAILED STEPS

	Command or Action	Purpose
Step 1	If your module depends on JARs that are not provided with the sample source code, include the jars in the <code>build.xml</code> file so that they are packaged in the zip file.	The following example shows a module layout with a third-party JAR: <pre>feature-oabc feature oabc.jar oabc lib flex flex-messaging-common.jar oabc.feature</pre>

	Command or Action	Purpose
		<p>The module jar and <code>.feature</code> are at the top level of the zip file. We recommend that you put the third-party jars under the <code>/moduleID/lib</code> folder path, then any other sub-directories you may want to add.</p> <pre data-bbox="643 436 1369 573"> { jars: ['features/feature-oabc.jar', features/oabc/lib/flex-messaging-common.jar], features: ["com.cloupia.feature.oabc.OABCModule"] } </pre> <p>When you list the jars in the <code>.feature</code> file, ensure that the jars start with <code>features/</code>; this is mandatory. This convention enables you to include the path to the jar. The path of each jar must be the same path that is used in your zip file. We recommend that you put your module jar first, followed by its dependencies, to ensure that your module loads.</p>
Step 2	From the <code>build.xml</code> file, run the ANT target build.	The zip file is generated and saved to the base directory of your project. (We recommend that you create your own project directory for your module. For convenience, in this example we assume that the sample project is the base directory for your project.)

Deploying a Module on Cisco UCS Director

The Cisco UCS Director user interface provides **Open Automation** controls that you can use to upload and manage modules. Use these controls to upload the zip file of the module to Cisco UCS Director.



Note Only zip-formatted files can be uploaded using the **Open Automation** controls.

Before You Begin

Acquire shell administrator access on the Cisco UCS Director VM. You can get this access from your system administrator. To use the Cisco UCS Director Shell Menu as a shell administrator, use SSH to access Cisco UCS Director, using the login **shelladmin** with the password that you got from the administrator.

For SSH access in a Windows system, use PuTTY (see <http://www.putty.org/>). On a Mac, use the built-in terminal application's SSH utility.

Step 1 Choose **Administration > Open Automation**.

Step 2 On the **Open Automation** page, click **Modules**.
The **Modules** page displays the following columns:

Column	Description
ID	The ID of the module.

Column	Description
Name	The name of the module.
Description	The description of the module.
Version	The current version of the module. The module developer must determine how to administer versioning of the module.
Compatible	Which version of Cisco UCS Director best supports this module.
Contact	The contact information of the person responsible for technical support for the module.
Upload Time	The time at which the module was uploaded.
Status	<p>The status of the module. Possible statuses are: Enabled, Disabled, Active, and Inactive.</p> <p>You can control whether a module is enabled or disabled. If enabled, Cisco UCS Director attempts to initialize the module; if disabled, Cisco UCS Director ignores the module. A module is set to the Active state only when Cisco UCS Director is able to successfully initialize the module without throwing an exception.</p> <p>Note Active does not necessarily mean that everything in the module is working properly; it merely indicates that the module is up. Inactive means that when Cisco UCS Director tried to initialize the module, a severe error prevented it from doing so. Typical causes for the Inactive flag are: the module is compiled with the wrong version of Java, or a class is missing from the module.</p>
Validated	Indicates whether the module is validated or not.

Note To enable module activation on upload, ensure that the `.feature` file in your module is named after your module ID. For example: If `moduleId` is `myFeatureName`, then name your feature file `myFeatureName.feature`.

The Cisco UCS Director framework identifies and loads the `.feature` file by name, based on the module ID. If the name of the `.feature` file and the module ID are different, the `.feature` file does not load and the module is not activated. If you choose to give the module ID and the `.feature` file different names, you must restart Cisco UCS Director to activate the module.

Step 3 Click **Add** to add a new module.

The **Add Modules** dialog box appears.

Step 4 Choose the module zip file from your local files and click **Upload** to upload the module zip file.

Step 5 Enable the module by choosing the module in the **Modules** table and clicking **Enable**.

Step 6 Wait while Cisco UCS Director activates the module.

Note Restarting Cisco UCS Director is not required to enable, disable, delete, or modify a module.

What to Do Next

Once the module is active, you can test the module.

Deleting, Deactivating, and Modifying Connectors

In addition to creating new connectors, you can also:

- Disable connectors
- Modify connectors (install new connector versions)
- Delete connectors from Cisco UCS Director

In previous releases, Cisco UCS Director had to be restarted for these changes to take effect. This restart is no longer required.

