

# Cisco Unified Virtualized Voice Browser (CVB) تي بي ثل تاو طخ

## تا يو ت ح م ل ا

[ة م د ق م ل ا](#)

[ة ي س ا س أ ل ا ت ا ب ل ط ت م ل ا](#)

[ت ا ب ل ط ت م ل ا](#)

[ة م د خ ت س م ل ا ت ا ن و ك م ل ا](#)

[ت ي ب ث ل ل ا](#)

## ة م د ق م ل ا

CVB ل تي بي ثل تاو طخ دن ت س م ل ا اذ ه ف ص ي

Cisco TAC. ن م ن ي س د ن ه م ل ا ر ي ب ك ة ط س ا و ب ة م ه ا س م ل ا ت م ت

## ة ي س ا س أ ل ا ت ا ب ل ط ت م ل ا

### ت ا ب ل ط ت م ل ا

د ن ت س م ل ا اذ ه ل ة ص ا خ ت ا ب ل ط ت م د ج و ت ال

### ة م د خ ت س م ل ا ت ا ن و ك م ل ا

CVB 11.0 ة ف ا ض ت س م ل ا ة ئ ي ب ل ا ل ا د ن ت س م ل ا اذ ه ي ف ة د ر ا و ل ا ت ا م و ل ع م ل ا د ن ت س ت

ة ص ا خ ة ي ل م ع م ة ئ ي ب ي ف ة د و ج و م ل ا ة ز ه ج أ ل ا ن م د ن ت س م ل ا اذ ه ي ف ة د ر ا و ل ا ت ا م و ل ع م ل ا ا ش ن ا م ت ت ن ا ك ا ذ ا (ي ض ا ر ت ف ا). ح و س م م ن ي و ك ت ب د ن ت س م ل ا اذ ه ي ف ة م د خ ت س م ل ا ة ز ه ج أ ل ا ع ي م ج ت ا د ب ر م ا ي أ ل ل م ت ح م ل ا ر ي ث ا ت ل ل ك م ه ف ن م د ك أ ت ف ، ة ر ش ا ب م ك ت ك ب ش

## ت ي ب ث ل ل ا

CVB ت ي ب ث ل ل ا ة م ز ا ل ل ا ت ا و ط خ ل ا ي ه ه ذ ه

ج ت ن م ل ا د د ح CVB ل ل ي غ ش ل ل ل ب ا ق ل ل ط و غ ض م ل ا ص ر ق ل ل ن م د ي ه م ت ل ا ب م ق 1. ة و ط خ ل ا ه ت ي ب ث ل ل ا ب و ل ط م ل ا

## Product Deployment Selection

Select the product or product suite to be installed:

(\*) Cisco Unified Voice Browser

CVB تېبىت دېكأت 2. ةوطخال

## Proceed with Install

Versions on the hard drive: NONE

The version on this DVD is: 11.0.0.95000-390  
Do you want to proceed with the Install?


Yes

No


يساسألماظنلا تېبىت جلاعمل ةعباتم رتخأ 3. ةوطخال




تثبيت كيدل سي ل لاثم الاذه في، ححصت لالتثبيت ل احيصل الاريال رتخأ. 4. ةوطخال احيصت



تثبيت لة عباتم ل قوف رونا. 5. ةوطخال



تثبيت التللي نيزم لة قطن م لار تخأ. 6 ة و ط خ ل ا



يئ ا ق ل ل ت ل ا ض و ا ف ت ل ا ن ي و ك ت ل ت ي ت ب ت ل ل ا ة ع ب ا ت م . 7 ة و ط خ ل ا

## Auto Negotiation Configuration

NIC speed and duplex in a virtual machine are determined by the Host.

They do not need to be configured in the Guest.

Please select "Continue" to proceed with the installation.

Continue

Back

(MTU) لقرنل لى صقألا دحلأة دحول يضرار تفالأ مآحلأا لى ع ظافحلأا 8 ةوطخلأا

## MTU Configuration

Do you want to change the MTU size from the OS default?

No

Yes

Back

Help

مدآخلأا لى صافات لآدأا 9 ةوطخلأا

**Static Network Configur**

Host Name vob1\_\_\_\_\_

IP Address 10.66.74.47\_\_\_\_\_

IP Mask 255.255.255.0\_\_\_\_\_

GW Address 10.66.74.1\_\_\_\_\_

**OK** **Back**

مداخل اب ةصاخ ل DNS لي صافات لخدأ 10. ةوطخال

**DNS Client Configuration**

Primary DNS 10.66.74.162\_\_\_\_\_


Secondary DNS (optional) \_\_\_\_\_

Domain parent.icm\_\_\_\_\_

م دخت س م ل ا تاغ و س م ل خدأ 11. ةوطخال



ةسسؤملا ليصافات لخدأ. 12 ةوطخلا



ىلوالا ةدقءلك اهءءءءءب مق. 13 ةوطخلا

## First Node Configuration

Is this server the First Node in the cluster?

Yes

No

Back

Help

جیحصل ال NTP ناو نع طقت ال. 14 ةوطخ ال

## Network Time Protocol Client Configuration

NTP Server 1

10.66.74.10\_\_\_\_\_

NTP Server 2

\_\_\_\_\_

NTP Server 3

\_\_\_\_\_

NTP Server 4

\_\_\_\_\_

NTP Server 5

\_\_\_\_\_

OK

Back


Help

عیمجت لل اهم ادختس! متيس يتل نامأل رورم ةم لك ريفوتب مق. 15 ةوطخ ال





SMTP فيضم إلى إعدادات نكت مل إذا ال ددح. 16. ةوطخا



قريب طال المدخات سم تاغوسم لخدأ. 17. ةوطخا

## Application User Configuration

The Application User username and password are used to log into the Application administrative webpage(s).

Application User Username  
Application User Password  
Confirm Application User Password

OK

Back

Help

تثبيت التاوطخ لمكأ. 18 ةوطخلا

## Platform Configuration Confirmation

The Platform Configuration is complete.

Select OK to continue or Back to change the configuration.

Warning: Once you select OK, you will no longer be able to modify the Platform Configuration.

OK

Back


Cancel

CVB قيبطت لوؤسم ةحفص حتفا ،تثبيت التاوطخ لامتكا درجمب. 19 ةوطخلا  
<https://<CVVB>/appadmin>

## License Information

 Next

Status

 Status : Ready

Click Next to proceed with 60 days demo license or Browse to select other options.


Enter a license or zip file name

License File

Browse...

Next

قلاسر رهظت ، حاجن ب صيخرتال رشن درجم ب . هرشن بجي يذلا صيخرتال ضارعتسا . 20 ةوطخلا ةحصلا نم ققحتال لامك .

 Status : Ready

Click Next to proceed with 60 days demo license or Browse to select other options.

Enter a license or zip file name

License File

Browse...



Validating uploaded license file...

Validation completed.


Please click on Next to continue.

CVB لىل ءانوكملا طيشنت متي . 21 ةوطخلا

Component Activation

 Back  Next

Status

 Components Activation is in progress, please wait.....

Component Name	Status
Cisco Unified Intelligence Center Reporting	Activated
Cisco VVB Config Datastore	Activating...
Cisco VVB Engine	Activating...
Cisco VVB Historical Datastore	Activating...
Cisco VVB Node Manager	Activated
Cisco VVB Repository Datastore	Activating...

Back Next

لحلالي ف مدختسملا بسانملا زيمرتال جامانرب دح . 22 ةوطخلا



## System Parameters Configuration

Back Next

Codec

G711U  
G711A

Back

Next



\*- indicates required item

لحلل اق فو ة ل ل ن ي و ك ت ف ي ر ع ت ب م ق . 23 ة و ط خ ل ا

## Languages Configuration

Back Next

Status



Status : Ready

IVR Language Configuration

	Language Group	Group Default
<input type="text" value="English"/>	en_AU	<input type="radio"/>
	en_CA	<input type="radio"/>
	en_GB	<input type="radio"/>
	en_US	<input checked="" type="radio"/>

Back

Next




The system default IVR Language is "en\_US". This can be m

ل ي غ ش ت ة د ا ع | م ت ت ، ح ا ج ن ب ن ي و ك ت ل ا ل ا م ت ك ا د ر ج م ب . 24 ة و ط خ ل ا C V B .

## Cisco VVB Setup Result Information

Cisco VVB Setup Status.	Cisco VVB Setup completed.
Cisco Unified SIP Configuration Status.	Cisco Unified SIP Configuration is done.
License Upload Status.	License Upload is done.
Publisher Activation Status.	Publisher Activation is done.
Cisco VVB Historical Datastore	Publisher is Activated
Cisco VVB Repository Datastore	Publisher is Activated
System Paramters update Status.	System Parameter Configuration is done.
Language update Status.	Language Configuration is done.
User configuration Status.	User Configuration is done.
Setup completed. The Cisco VVB Engine is restarting.	

 Please close your web browser now!

نېوكتلل CVB رفوتې 25. ةوطخلال



### Cisco Virtualized Voice Browser Administration

For Cisco Unified Communications Solutions

System Applications Subsystems Tools Help

## Cisco Virtualized Voice Browser Administration

System version: 11.0.0.95000-390

Copyright © 1999-2014 Cisco Systems, Inc.  
All rights reserved

This product contains cryptographic features and is subject to United States and local country laws governing import, export, transfer and use. Do not export or re-export this product without obtaining the necessary export license from the U.S. Department of Commerce. If you are unable to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at: <http://www.cisco.com/wwl/export/crypto/tool/stqrg.html>.  
If you require further assistance please contact us by sending email to [export@cisco.com](mailto:export@cisco.com).

ةمچرتل هذه ل و ح

ةلأل تاي نقتل ن م ة و مچ م ادخت ساب دن تسمل اذ ه Cisco ت مچرت  
ملاعلاء ن أ عي مچ ي ف ن ي م دخت سمل ل معد ي و تح م مي دقت ل ة يرش ب ل و  
امك ة ق ي قد ن و ك ت ن ل ة ل أ مچرت ل ض ف أ ن أ ة ظ حال م ي ج ر ي . ة ص ا خ ل م ه ت غ ل ب  
Cisco ي ل خ ت . ف ر ت ح م مچرت م ا ه م د ق ي ي ت ل ا ة ي ف ا ر ت ح ا ل ا ة مچرت ل ا ع م ل ا ح ل ا و ه  
ي ل ا م ا د ع و ج ر ل ا ب ي ص و ت و ت ا مچرت ل ا ه ذ ه ة ق د ن ع ا ه ت ي ل و ئ س م Cisco  
Systems (رف و ت م ط بار ل ا) ي ل ص أ ل ا ي ز ي ل ج ن ا ل ا دن تسمل ا