

# Verifique a versão das atualizações na CLI (Command Line Interface, interface de linha de comando) do Firepower

## Contents

[Introdução](#)

[Pré-requisitos](#)

[Abreviaturas](#)

[Verificar Versão de Atualizações Diferentes](#)

[1. Versão do Software do Produto](#)

[2. SRU e versão de atualização VDB](#)

[3. Versão de Atualização do GeoDB](#)

## Introdução

Este documento descreve como verificar diferentes versões de atualizações na CLI (Command Line Interface, interface de linha de comando) do Firepower.

## Pré-requisitos

A Cisco recomenda que você tenha conhecimento sobre estes produtos:

- Firepower Management Center (FMC)
- Firepower Threat Defense (FTD)

## Abreviaturas

- Firepower Management Center (FMC)
- Firepower Threat Defense (FTD)
- Atualização de regra segura ou Atualização de regra Sourcefire (SRU)
- Pacote de segurança leve (LSP)
- Banco de dados de vulnerabilidade (VDB)
- Banco de Dados GeoLocation (GeoDB)

## Verificar Versão de Atualizações Diferentes

## 1. Versão do Software do Produto

No FMC e no FTD CLI, você pode verificar se a versão do software do produto está sendo executada atualmente pelo comando:

```
show version
```

Exemplo: saída de comando do FMC CLI.

```
Copyright 2004-2023, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.
```

```
Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 499)  
Cisco Secure Firewall Management Center for VMware v7.2.4 (build 169)
```

```
>  
> show version  
-----[ FMC ]-----  
Model                : Secure Firewall Management Center for VMware (66) Version 7.2.4 (Build 169) <-  
UUID                 : 6308d00c-54c3-11ee-a889-c4b0f35cec33  
Rules update version: 2023-10-02-002-vrt  
LSP version          : lsp-rel-20231002-1553  
VDB version          : 372  
-----
```

Exemplo: saída de comando da CLI do FTD.

```
Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.
```

```
Cisco Firepower Extensible Operating System (FX-OS) v2.10.1 (build 1400)  
Cisco Firepower Threat Defense for VMware v7.0.5 (build 72)
```

```
>  
> show version  
-----[ FTD ]-----  
Model                : Cisco Firepower Threat Defense for VMware (75) Version 7.0.5 (Build 72) <- - Di  
UUID                 : 48797b40-463e-11ed-92b0-d0e26b47dcc4  
Rules update version : 2023-10-02-002-vrt  
VDB version          : 372  
-----
```

## 2. SRU e versão de atualização VDB

No FMC e no FTD CLI, você pode verificar a versão de atualização de SRU (Snort2) e LSP (Snort3) e a versão do VDB em execução no momento pelo comando:

show version

Exemplo: saída de comando do FMC CLI.

Copyright 2004-2023, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.

Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 499)  
Cisco Secure Firewall Management Center for VMware v7.2.4 (build 169)

```
>
> show version
-----[ FMC ]-----
Model           : Secure Firewall Management Center for VMware (66) Version 7.2.4 (Build 169)
UUID            : 6308d00c-54c3-11ee-a889-c4b0f35cec33
Rules update version: 2023-10-02-002-vrt                <- - Display installed SRU (Snort2) vers
LSP version     : lsp-rel-20231002-1553                <- - Display installed LSP (Snort3) ver
VDB version     : 372                                  <- - Display running VDB version.
-----
```

Exemplo: saída de comando do FTD CLI Snort2.

Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.

Cisco Firepower Extensible Operating System (FX-OS) v2.10.1 (build 1400)  
Cisco Firepower Threat Defense for VMware v7.0.5 (build 72)

```
>
> show version
-----[ FTD ]-----
Model           : Cisco Firepower Threat Defense for VMware (75) Version 7.0.5 (Build 72)
UUID            : 48797b40-463e-11ed-92b0-d0e26b47dcc4
Rules update version : 2023-10-02-002-vrt                <- - Display running SRU (Snort2) vers
VDB version     : 372                                  <- - Display running VDB version.
-----
```

Exemplo: saída de comando do FTD CLI Snort3.

Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.

Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 8)  
Cisco Firepower Threat Defense for VMware v7.2.0 (build 18)

```
>
> show version
```

```

-----[ FTD ]-----
Model       : Cisco Firepower Threat Defense for VMware (75) Version 7.2.0 (Build 18)
UUID        : c04f9496-db0e-11ed-81a1-942878af0a8c
LSP version  : lsp-rel-20231002-1553                <- - Display running LSP (Snort3) vers
VDB version  : 372                                  <- - Display running VDB version.
-----

```

### 3. Versão de Atualização do GeoDB

No FMC e FTD CLI (no modo especialista), você pode verificar a versão atual do GeoDB pelo comando:

```
cat /var/sf/geodb/country_code_map_version
```

Exemplo: saída de comando do FMC CLI.

Copyright 2004-2023, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.

```

Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 499)
Cisco Secure Firewall Management Center for VMware v7.2.4 (build 169)
>
> expert
rirana@FMC:~$ sudo su -
Password:
root@FMC:~#
root@FMC:~# cd /var/sf/geodb/
root@FMC:/var/sf/geodb#
root@FMC:/var/sf/geodb# cat country_code_map_version                <- - To display running GeoDB update version
2023-09-25-100                                                    <- - FMC GeoDB update version is 2023-09-25-

```

Exemplo: saída de comando da CLI do FTD.

Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.

```

Cisco Firepower Extensible Operating System (FX-OS) v2.10.1 (build 1400)
Cisco Firepower Threat Defense for VMware v7.0.5 (build 72)
>
> expert
FTD:~$ sudo su -
Password:
root@FTD:~#
root@FTD:~# cd /var/sf/geodb/
root@FTD:geodb#
root@FTD:geodb# cat country_code_map_version                <- - To display running GeoDB update version.
2023-09-25-100                                                    <- - FTD GeoDB update version is 2023-09-25-1

```



## Sobre esta tradução

A Cisco traduziu este documento com a ajuda de tecnologias de tradução automática e humana para oferecer conteúdo de suporte aos seus usuários no seu próprio idioma, independentemente da localização.

Observe que mesmo a melhor tradução automática não será tão precisa quanto as realizadas por um tradutor profissional.

A Cisco Systems, Inc. não se responsabiliza pela precisão destas traduções e recomenda que o documento original em inglês ([link fornecido](#)) seja sempre consultado.