

# **Manage Users**

• Manage Users, on page 1

## **Manage Users**

## **Configure User Roles and Invite Users**

Cisco Spaces: Detect and Locate users have role-based access control (RBAC), where users or groups of users are provided with various user roles. User roles have different restrictions based on the permissions that are associated with each role. The available permissions are **AdminAccess**, **ReadOnlyAccess**, and **SiteAdminAccess** and these define the locations and sites an associated user has access to. A user's Cisco Spaces: Detect and Locate dashboard displays only those locations that are defined for the particular user role.

#### Table 1: Permissions and Privileges

Permissions	Privilege
AdminAccess	Read and write access to entire system.
ReadOnlyAccess	Read only access.
SiteAdminAccess	Read and write access at site-level.

#### Before you begin

Upload maps.

#### Procedure

Step 1	In the left navigation pane, click User Management > User Roles. From the Roles window, Click the Add button.
--------	---

- **Step 2** In the **Role** window, do the following:
  - a) **Name**: Enter a name for the user role.
  - b) **Permission**: Choose a permission from the drop-down list.
  - c) Choose specific Sites from the drop-down list.

Role	
Name*	
Permission*	~
Sites*	
BDLK09 Campus	AII
<ul> <li>System Campus</li> </ul>	

**Step 3** Invite users by entering their email IDs and choosing a **Role** as configured in Step 2.

	Invite user	×
Email*		
Role*		~
	Cancel Save	

### **Modifying Users and User Roles**

You, as an administrator, cannot modify the personal details of a user. The user also cannot modify his personal details from the **User Management** window.

The Detect and Locate Administrator can modify User Roles only. The Detect and Locate Administrator can edit the role of a specific user by editing user details from **User Management > App Users**.

Users listed under **User Management > Administrators** are administrators defined in the Cisco Spaces dashboard. This type of user cannot be edited from Detect and Locate, and can be edited from the Cisco Spaces dashboard only.

#### Procedure

Step 1 To modify user details, users must log in to their respective accounts on the Detect and Locate dashboard and navigate to User Settings.

L




Figure 1: Modifying personal details from User Settings

- **Step 2** From the **Preferences** tab, you can set the following
  - Map auto refresh (in seconds): Select how often your location list and map refreshes automatically to reflect your assets' movement.
  - Client display icon: Decide how a client is to be represented on the Detect and Locate dashboard.
  - AP Label Setting
  - Enable Sticky Clients
- **Step 3** From the **Account Activity** tab, you can observe dasboard access activity, such as browsers used, access time, and location.

I

■ Cisco DNA Space	Detect and Locate			
y Account				
0				
	My Profile	Account Activity	Preferences	
Browser	Last Access	Location		
Firefox. v 77	Jun 16th, 2020 02:21:38 PM	Bengaluru,IN		
Browser	Last Access	Location		
Firefox. v 76	Jun 2nd, 2020 10:37:19 PM	Bengaluru,IN		
Browser	Last Access	Location		
Firefox. v 76	May 27th, 2020 04:06:33 PM	Bengaluru,IN		
Browser	Last Access	Location		
		Bengaluru, IN		